



**DOS UTILITIES
SOURCE LISTING
(DOS II)**



A Warner Communications Company 

C017894

DOS UTILITIES
SOURCE LISTING
(DOS II)

NOTICE

TO ALL PERSONS RECEIVING THIS DOCUMENT

AUGUST 1981

REPRODUCTION IS FORBIDDEN WITHOUT THE SPECIFIC
WRITTEN PERMISSION OF ATARI, INC. SUNNYVALE, CA.
94086. NO RIGHT TO REPRODUCE THIS DOCUMENT, NOR
THE SUBJECT MATTER THEREOF, IS GRANTED UNLESS BY
WRITTEN AGREEMENT WITH, OR WRITTEN PERMISSION
FROM THE CORPORATION.

MANUAL CONTENTS © 1981 ATARI, INC.

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 1

1
2
3
4
5
6
7
8
9
10
11
12
13
14

TITLE 'DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80'
LIST X

;
;
; CHANGED FOR SYSTEM RESET -- DUPFLG
; ADDED INTERRUPT ROUTINES FROM SIO -- KB
; ADDED SAVE/RESTORE OF DOSINI VECTOR -- KB
;

; THIS IS FINAL VERSION OF DUP --- 2.05 ---
; *****

;
; FILENAME = DOS2.DUP205 ON TANDEM
;

```

15
16
17
18
19
20 E456      CIO      =      $E456
21 E453      DKHND    =      $E453
22 E45C      SETVBV   =      $E45C
23 E45F      SYSVBV   =      $E45F
24 E462      XITVBV   =      $E462
25 E46E      CIOINV   =      $E46E
26 02E5      MEMTOP   =      $2E5
27 0011      BRKKEY   =      $11
28 000A      DOSVEC   =      $A
29 000C      DOSINI   =      $C      ; DOS INIT VECTOR
30 0008      WARMST    =      $B
31 0052      LMARGN   =      $52
32 0053      RMARGN   =      $53
33 BFFA      CARTST   =      $BFFA
34 020A      INTRVEC   =      $20A      ; INTERRUPT VECTOR LOC FOR SIO PATCH
35 02E7      MEMLO    =      $2E7
36 02BE      SHFLOK   =      $2BE
37 02E2      INITAD   =      $2E2
38 02E0      RUNAD    =      $2E0
39 0020      ICHIDZ   =      $20
40 0021      ICDNOZ   =      $21
41 0024      ICBALZ   =      $24
42 0025      ICBABZ   =      $25
43 002E      ICIDNO   =      $2E
44 0021      MAXDEV   =      $21
45 031A      HATABS   =      $31A
46 1700      USRDOS   =      $1700
47 0700      FMS      =      $700
48 07E0      FMINIT   =      FMS+$E0
49 1540      DOS      =      FMS+$E40
50 E474      WRMSTR    =      $E474      ; WARM START VECTOR
51 0772      BSIOR     =      $772      ; ENTRY POINT TO FMS DISK HANDLER USED BY
52 021C      CDTMV3    =      $21C      ; ADDRESS OF SYSTEM TIMER # 3
53 022A      CDTMF3    =      $22A      ; ADDRESS OF SYS TIMER # 3 TIME OUT FLAG
54
55 009B      CR        =      $9B
56 001C      CUP        =      $1C
57 001D      CDN        =      $1D
58 001E      CLF        =      $1E
59 001F      CRT        =      $1F
60 009C      DLL        =      $9C
61 007D      CLSCR      =      $7D
62 0088      EOF        =      $88      ; ENDFILE RETURN CODE FROM CIO
63
64
65 0003      OPEN       =      $03
66 000C      CLOSE      =      $0C
67 000B      PUTCHR     =      $0B
68 0007      GETCHR     =      $07

```

69	0005	GETREC	=	\$05	
70	0009	PUTREC	=	\$09	
71	0020	RENAME	=	\$20	
72	0021	DELETE	=	\$21	
73	00FE	FORMAT	=	\$FE	
74	0023	LOCK	=	\$23	
75	0024	UNLOCK	=	\$24	
76	0053	STAREQ	=	\$53	
77					; STATUS COMMAND TO DISK CONTROLLER
78	0010	IOCB1	=	\$10	
79					
80	02EA	DVSTAT	=	\$2EA	; ADDRESS OF STATUS INFO STORED BY OS
81					
82					
83	0300	DCB	=	\$300	
84	0301	DUNIT	=	DCB+1	
85	0302	DCOMND	=	DCB+2	
86	0303	DSTATS	=	DCB+3	
87	0304	DBUFLO	=	DCB+4	
88	0305	DBUFHI	=	DCB+5	
89	030A	DSLO	=	DCB+\$A	
90	030B	DSHI	=	DCB+\$B	
91					
92	0340	IOCB	=	\$340	
93	0340	ICHID	=	IOCB+0	
94	0341	ICDNO	=	IOCB+1	
95	0342	ICCOM	=	IOCB+2	
96	0343	ICSTA	=	IOCB+3	
97	0344	ICBAL	=	IOCB+4	
98	0345	ICBAH	=	IOCB+5	
99	034B	ICBLL	=	IOCB+8	
100	0349	ICBLH	=	IOCB+9	
101	034A	ICAX1	=	IOCB+10	
102	034B	ICAX2	=	IOCB+11	
103					
104	0000	SYSED	=	\$0	
105	0008	QWRIT	=	\$08	
106	000C	ORDWRT	=	\$0C	
107					
108		HILO	. MACRO	P1	
109		P1&H	=	P1&/256	
110		P1&L	=	(-256)*&P1&H+&P1	
111			. ENDM		

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 4

112

113

114

115

116

117 0018

118 001A

119 001A

PAGE

; **** ZERO PAGE VARIABLES ****

;

;

*= \$18

JMPTBL: RES 2

RAMLO: RES 2

BUFADR = RAMLO

; SAVE AREA FOR BUFFER ADDRESS USED BY US


```

120
121
122
123
124
125
126
127
128 1540 A9 00
129 1542 8D 9E 15
130 1545 A9 9F
131 1547 85 0A
132 1549 A9 17
133 154B 85 0B
134 154D A9 23
135 154F 8D 0A 02
136 1552 A9 1A
137 1554 8D 0B 02
138 1557 A9 E6
139 1559 8D 0C 02
140 155C A9 19
141 155E 8D 0D 02
142 1561 20 E0 07
143 1564 A5 0B
144 1566 D0 15
145 1568 A9 0C
146 156A 8D 54 03
147 156D A9 17
148 156F 8D 55 03
149 1572 20 93 15
150 1575 A9 C0
151 1577 20 A6 15
152 157A 4C AA 19
153
154 157D AD 9D 15
155 1580 F0 11
156
157 1582 AD 9E 17
158 1585 F0 12
159 1587 20 3F 19
160
161 158A 20 2E 19
162 158D 20 93 15
163 1590 20 74 E4
164
165 1593 A9 00
166 1595 8D 9D 15
167 159B 60
168
169 1599 85 0B
170 159B F0 F6

```

PAGE
 **** INIT CODE FOR DUP ****
 INITIALIZATION CODE FOR DUP - CALLS FMS INIT CODE.
 CALLED ON WARM START AND COLD START.

```

    *=      DOS
    LDA     #0
    STA     OPT
    LDA     #.LOW.MNDUPL
    STA     DOSVEC
    LDA     #.LOW.MNDUPH
    STA     DOSVEC+1
    LDA     #.LOW.ISRSIR
    STA     INTRVEC
    LDA     #.HIGH.ISRSIR
    STA     INTRVEC+1
    LDA     #.LOW.ISRODN
    STA     INTRVEC+2
    LDA     #.HIGH.ISRODN
    STA     INTRVEC+3
    JSR     FMINIT
    LDA     WARMST
    BNE     CKMDOS
    LDA     #.LOW.AFL
    STA     ICBAL+$10
    LDA     #.LOW.AFH
    STA     ICBALH+$10
    JSR     INITX
    LDA     #$C0
    JSR     STLOAD
    JMP     CLOSX
    CKMDOS  LDA     DUPFLG
    BEQ     INITX
    LDA     MEMFLG
    BEQ     CLDSET
    JSR     LDMEM1
    JSR     RELDIN
    JSR     INITX
    JSR     WRMSTR
    INITX   LDA     #0
    STA     DUPFLG
    RTS
    CLDSET  STA     WARMST
    BEQ     INITX

```

; SET UP INTERRUPT VECTORS FOR SIO PATCH.
 ; INSTEAD OF USING THE SERIAL INPUT READY
 ; SERVICE ROUTINE AND THE SERIAL OUTPUT
 ; INTERRUPT SERVICE ROUTINE IN THE OS ROM
 ; USE THE VERSIONS IN RAM FOLLOWING THE
 ; RESIDENT PORTION OF DUP
 ; ON COLDSTART, LOAD AUTORUN.SYS
 ; WARMSTART CHECK IF DUP WAS RUNNING
 ; CLEAR DUPFLG SHOW DUP NOT IN MEMORY.
 ; LOAD, INIT AND RUN THE AUTORUN FILE
 ; MAKE SURE IOCB #1 IS CLOSED & RETURN
 ; SEE IF DUP WAS IN MEMORY
 ; =ZERO THEN WASN'T
 ; SEE IF USER AREA WRITTEN TO MEM.SAV
 ; =ZERO THEN WASN'T
 ; ELSE GET USER MEMORY BACK IN
 ; RELOAD SAVED DOSINI VECTOR
 ; CLEAR DUP IN MEMORY FLAG
 ; REDO WARMSTART
 ; SAY DUP NOT IN MEMORY
 ; CLEAR FLAG
 ; NO VALID USER MEMORY
 ; SET TO COLD START

```

171      PAGE
172      ****  LOADER ROUTINE  ****
173
174
175      LOADS FROM THE FILE (MUST BE LOAD FORMAT)
176      INTO MEMORY. RETURNS:
177          X=0 LOAD OK
178          X=1 OPEN ERRORS Y=CIO CODE
179          X=2 READ ERRORS Y=CIO CODE
180          X=3 BAD LOAD FILE
181      ON ENTRY, IOCB 1 POINTS TO FILENAME.
182
183      159D 00      DUPFLG .BYTE 0      ; FLAG -IF DUP IN MEMORY NOT ZERO
184      159E 00      OPT     .BYTE 0      ; HOLDS VALUE OF OPTION GIVEN BY USER
185      159F 00      LOADFG  .BYTE 0      ; FLAG = $80 IF MEMORY FILE DOESN'T HAVE
186      15A0          HDBUF: .RES 4
187      15A4          HILO   HDBUF
188      0015          +HDBUFH = HDBUF/256
189      00A0          +HDBUFL = (-256)*HDBUFH+HDBUF
190      15A4
191      15A4 A9 80      SFLOAD LDA    $$80
192      15A6 8D 9F 15  STLOAD STA    LOADFG
193      15A9 A9 47      LOAD   LDA    $.LOW.RTS
194      15AB 8D E0 02      STA    RUNAD
195      15AE A9 16      LDA    $.HIGH.RTS
196      15B0 8D E1 02      STA    RUNAD+1      ; MAKE RUN AT EOF DEFAULT TO RTS
197      15B3 A2 10      LDX    $$10
198      15B5 A9 03      LDA    #OPEN
199      15B7 9D 42 03      STA    ICCOM,X
200      15BA A9 04      LDA    #4      ; OPEN TYPE=INPUT
201      15BC 9D 4A 03      STA    ICAX1,X
202      15BF 20 56 E4      JSR    CIO      ; TRY TO OPEN FILE
203      15C2 10 04      BPL    RDLF      ; CONT IF OK
204      15C4 A9 01      LDA    #1      ; OPEN ERRORS
205      15C6 D0 7E      BNE    CLFX      ; CLOSE AND EXIT
206      15C8 A2 10      RDLF  LDX    $$10
207      15CA A9 F4      LDA    $.LOW.DBUFL
208      15CC 9D 44 03      STA    ICBAL,X
209      15CF A9 1D      LDA    $.LOW.DBUFH
210      15D1 9D 45 03      STA    ICBAH,X
211      15D4 A9 02      LDA    #2
212      15D6 9D 48 03      STA    ICBLL,X
213      15D9 A9 00      LDA    #0
214      15DB 9D 49 03      STA    ICBLLH,X
215      15DE 8D 0B 17      STA    MEMLDD      ; CLEAR MEM.SAV LOADED FLAG
216      15E1 A9 07      LDA    #GETCHR
217      15E3 9D 42 03      STA    ICCOM,X
218      15E6 20 56 E4      JSR    CIO
219      15E9 30 64      BMI    ERST      ; IF ERRS
220      15EB A9 FF      LDA    $$FF
221      15ED CD F4 1D      CMP    DBUF      ; CHECK FOR VALID LOAD FILE
222      15F0 D0 56      BNE    LNLF
223      15F2 CD F5 1D      CMP    DBUF+1
224      15F5 D0 51      BNE    LNLF      ; BRANCH IF NOT A LOAD FILE

```

```

225 15F7 A2 10
226 15F9 A9 A0
227 15FB 9D 44 03
228 15FE A9 15
229 1600 9D 45 03
230 1603 A9 04
231 1605 9D 48 03
232 1608 A9 00
233 160A 9D 49 03
234 160D 20 56 E4
235 1610 10 46
236 1612 C0 88
237 1614 D0 39
238
239
240
241 1616 20 AA 19
242 1619 2C 9E 15
243 161C 30 03
244 161E 20 08 17
245 1621 A9 00
246 1623 2C 9F 15
247 1626 8D 9F 15
248 1629 30 1B
249 162B 20 73 18
250 162E 30 05
251 1630 68
252 1631 68
253 1632 4C B8 17
254
255
256
257
258 1635 AD 9D 15
259 1638 D0 0A
260 163A A9 1B
261 163C A2 17
262 163E 20 BE 19
263 1641 4C 01 18
264
265
266
267 1644 A9 00
268 1646 AA
269 1647 60
270
271
272
273 1648 20 AA 19
274 164B A9 03
275 164D D0 F7
276 164F 98
277 1650 48
278 1651 20 AA 19

RDDRRC LDX ##10
        LDA #. LOW. HDBUFL
        STA ICBAL, X
        LDA #. LOW. HDBUFH
        STA ICBAL, X
        LDA #4
RDDRRC1 STA ICBLL, X
        LDA #0
        STA ICBLL, X
        JSR CIO
        BPL STOK
        CPY ##88
        BNE ERST
; NO ERROR CHECK SO CAN CATCH EOF
; IF NO ERROR
; SEE IF EOF
; IF SOME ERROR STATUS

; EOF SO DONE, EXIT
;
        JSR CLOSX
        BIT OPT
        BMI DRUN
        JSR JMPRUN
        LDA #0
        BIT LOADFG
        STA LOADFG
        BMI CLFX
        JSR MEMSVQ
        BMI DRUN1
        PLA
        PLA
        JMP GOOD
; CLOSE IOCB'S 1 AND 2
; BRANCH IF NO RUN OPTION
; JUMP THROUGH RUN VECTOR
; OK STATUS
; WAS MEMORY SWAPPED?
; BRANCH IF MEMORY WASN'T SWAPPED
; DOES MEMORY SAVE FILE EXIST?
; BRANCH IF NOT
; WRITE MEMORY AND RELOAD DUP
;
        SEE IF DUP WRITTEN OVER. IF IS RELOAD & TELL USER NEED MEM. SAV T
        LOAD THIS FILE.
;
DRUN1 LDA DUPFLG
        BNE DRUN2
        LDA #. LOW. NMSFL
        LDX #. LOW. NMSFH
        JSR PRNMSG
        JMP RRDUP
; SEE IF DUP CLOBBERED
; NO, THEN RETURN
; ELSE TELL USER NEED MEM. SAV
; PRINT MSG
; RELOAD & RUN DUP
;
        RETURN TO CALLING ROUTINE
;
DRUN2 LDA #0
        CLFX TAX
        RTS RTS
; NO DUP ERR MSG ON EOF
;
; ERROR RETURNS
;
LNLF JSR CLOSX
        LDA #3
        BNE CLFX
ERST TYA
        PHA
        JSR CLOSX
; BAD LOAD FILE

```

```

279 1654 68          PLA
280 1655 AB          TAY
281 1656 D0 EE       BNE      CLFX
282
283                ;
284                ; CONTINUE WITH LOAD - CHECK LOAD ADDRESS FOR HEADER
285                ; HEADER IF HAVE CONCATENATED LOAD FILES
286 1658 A2 10       STOK     LDX      #$10
287 165A AD A0 15     LDA      HDBUF          ; MOVE PARAMS TO IOCB
288 165D 9D 44 03     STA      ICBAL, X
289 1660 48           PHA
290 1661 AD A1 15     LDA      HDBUF+1
291 1664 9D 45 03     STA      ICBAH, X
292 1667 AB          TAY
293 1668 68          PLA
294 1669 C8          INY
295 166A D0 1F       BNE      ADOK          ; WAS ADDRESS FF?
296 166C AB          TAY          ; BRANCH IF NOT
297 166D C8          INY
298 166E D0 1B       BNE      ADOK          ; OTHER BYTE FF?
299                ; BRANCH IF NOT
300
301                ; HAVE A HEADER & START ADDRESS - GET END ADDRESS FOR TEXT & DO AG
302 1670 AD A2 15     LDA      HDBUF+2
303 1673 8D A0 15     STA      HDBUF
304 1676 AD A3 15     LDA      HDBUF+3
305 1679 8D A1 15     STA      HDBUF+1          ; MOVE LOAD ADDRESS
306 167C A9 A2       LDA      #.LOW.HDBUF+2
307 167E 9D 44 03     STA      ICBAL, X
308 1681 A9 15       LDA      #.HIGH.(HDBUF+2)
309 1683 9D 45 03     STA      ICBAH, X          ; SO LOAD ADDRESS DOESN'T GET WIPED OUT B
310 1686 A9 02       LDA      #2
311 1688 4C 05 16     JMP      RDDRC1
312
313                ; GET LENGTH OF TEXT. THEN DETERMINE IF IN DUP
314
315 168B AD A2 15     ADOK     LDA      HDBUF+2
316 168E 38          SEC
317 168F ED A0 15     SBC      HDBUF
318 1692 9D 48 03     STA      ICBLL, X
319 1695 AD A3 15     LDA      HDBUF+3
320 1698 ED A1 15     SBC      HDBUF+1
321 169B 9D 49 03     STA      ICBLH, X
322 169E AD A1 15     LDA      HDBUF+1
323 16A1 20 FA 16     JSR      AWDG          ; IS BEGINNING ADDRESS WITHIN DUP?
324 16A4 B0 15       BCS      AWD          ; BRANCH IF SO
325 16A6 AD A3 15     LDA      HDBUF+3
326 16A9 20 FA 16     JSR      AWDG          ; IS ENDING ADDRESS WITHIN DUP?
327 16AC B0 0D       BCS      AWD          ; BRANCH IF SO
328
329                ; SINCE TEXT IN DUP, LOAD MEM.SAV IF NECESSARY
330
331 16AE AD 0B 17     ANWD     LDA      MEMLDD
332 16B1 30 0B       BMI      AWD          ; BRANCH IF MEM.SAV ALREADY LOADED

```

```

333 16B3 A9 80          LDA    ##80
334 16B5 0D 9F 15      ORA     LOADFG
335 16B8 8D 9F 15      STA     LOADFG
336 16BB FE 48 03      AWD     INC     ICBLL,X          ; SET MEM. SAV DOESN'T HAVE TO BE LOADED F
337 16BE D0 03          BNE     *+5
338 16C0 FE 49 03      INC     ICBLL,X
339 16C3 2C 9F 15      BIT     LOADFG          ; DOES MEMORY HAVE TO BE LOADED
340 16C6 30 13          BMI     DLM              ; BRANCH IF NOT
341 16C8 AD 0B 17      LDA     MEMLDD          ; WAS MEM. SAV ALREADY LOADED?
342 16CB 30 0E          BMI     DLM              ; BRANCH IF SO
343 16CD CE 0B 17      DEC     MEMLDD
344 16D0 20 39 19      JSR     LDMEM          ; LOAD MEM. SAVE FILE (IF IT EXISTS)
345 16D3 A9 00          LDA     #0              ; SHOW USER AREA NOT DUP IN MEMORY
346 16D5 8D 9D 15      STA     DUPFLG
347 16D8 20 2E 19      JSR     RELDIN          ; RESTORE DOS IN VECTOR FROM SAVED LOC
348
349
350
351 16DB A2 10          DLM     LDX     ##10
352 16DD A9 47          LDA     #.LOW.RTS
353 16DF 8D E2 02      STA     INITAD
354 16E2 A9 16          LDA     #.HIGH.RTS
355 16E4 8D E3 02      STA     INITAD+1          ; INIT DEFAULTS TO AN RTS
356 16E7 20 56 E4      JSR     CIO              ; READ DATA DIRECTLY TO MEMORY
357 16EA 10 03          BPL     DLM1
358 16EC 4C 4F 16      JMP     ERST              ; IF ERRORS
359 16EF 2C 9E 15      DLM1    BIT     OPT
360 16F2 30 03          BMI     DINIT          ; BRANCH IF NO GO OPTION
361 16F4 20 05 17      JSR     JMPINT          ; DO INIT
362 16F7 4C F7 15      DINIT    JMP     RDDRC          ; GET NEXT SECTION OF LOAD FILE
363
364
365
366
367
368
369 16FA C9 1D          AWDG    CMP     #.LOW.NDOSH
370 16FC 90 06          BCC     AWDGR          ; BRANCH IF HI BYTE LT DUP START
371 16FE C9 34          CMP     #.LOW.NMDUPH+1
372 1700 2A            ROL     A
373 1701 49 01          EOR     #1
374 1703 4A            LSR     A          ; COMPLEMENT CARRY
375 1704 60          AWDGR    RTS
376
377
378 1705 6C E2 02      JMPINT  JMP     (INITAD)
379 1708 6C E0 02      JMPRUN  JMP     (RUNAD)
380
381
382 170B 00          MEMLDD  .BYTE  0
383 170C 44 31 3A 41  AF      .BYTE  'D1: AUTORUN. SYS', CR
384 1710 55 54 4F 52
385 1714 55 4E 2E 53
386 1718 59 53 9B

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 10

387 171B
388 0017
389 000C
390 171B 4E 45 45 44
391 171F 20 4D 45 4D
392 1723 2E 53 41 56
393 1727 20 54 4F 20
394 172B 4C 4F 41 44
395 172F 20 54 48 49
396 1733 53 20 46 49
397 1737 4C 45 2E 9B
398 173B
399 0017
400 001B

HILO AF
+AFH = AF/256
+AFL = (-256)*AFH+AF
NMSF .BYTE 'NEED MEM. SAV TO LOAD THIS FILE. ',CR

HILO NMSF
+NMSFH = NMSF/256
+NMSFL = (-256)*NMSFH+NMSF

```

401 .PAGE
402 ; **** CREATE MEM.SAV FILE ****
403 ;
404 ;
405 ; ROUTINE WRITTEN BY M.E., APRIL 21, 1980
406 ; THIS ROUTINE CREATES A FILE ON DISK OF DATA FROM MEMORY
407 ; CREATE FILE CALLED 'D1:MEM.SAV', SET Y=1
408 ;
409 ; ABLE TO CREATE FILE THEN SET REG.Y=ERROR RETURNED FROM CIO
410 ; THE RAM TO BE OCCUPIED BY DUP IS STORED BY THIS ROUTINE INTO
411 ; 'MEMORY.SAV'
412 ;
413 ;
414 173B 44 31 3A 4D NAME . BYTE 'D1:MEM.SAV', CR
415 173F 45 4D 2E 53
416 1743 41 56 9B
417 1746
418 0017 +NAMEH = NAME
419 003B +NAMEL = (-256)*NAMEH+NAME
420 1746 20 AA 19 MWRITE JSR CLOSX ; CLOSE IOCB AND OPEN IT TO WRITE
421 1749 A9 0B LDA #OWRIT
422 174B 9D 4A 03 STA ICAX1, X
423 174E 20 79 17 JSR OREST ; OPEN FOR WRITE
424 1751 30 38 BMI ERRWR ; IF ERROR THEN JMP AND RET
425 ;
426 ;
427 ; WRITE MEMORY BLOCK
428 ;
429 1753 A9 0B LDA #PUTCHR
430 1755 9D 42 03 STA ICCOM, X
431 1758 A9 7C LDA #.LOW.NDOSL ; STORE START OF BLOCK FOR CIO
432 175A 9D 44 03 STA ICBAL, X
433 175D A9 1D LDA #.LOW.NDOSH ; START ADDR (HIGH)
434 175F 9D 45 03 STA ICBAH, X
435 1762 A9 8A LDA #.LOW.MLENL+1 ; LENGTH OF BLOCK
436 1764 9D 48 03 STA ICBLL, X
437 1767 A9 15 LDA #.LOW.MLENH ; LENGTH(HIGH)
438 1769 9D 49 03 STA ICBLH, X
439 176C 20 56 E4 JSR CIO ; WRITE DATA BLOCK
440 176F 30 1A BMI ERRWR ; IF WRITE ERROR THEN JMP
441 1771 20 AA 19 JSR CLOSX
442 1774 30 15 BMI ERRWR
443 1776 A0 00 LDY #0
444 1778 60 RET RTS
445 ;
446 1779 A9 03 OREST LDA #.LOW.OPEN
447 177B 9D 42 03 STA ICCOM, X
448 177E A9 3B LDA #.LOW.NAMEL ; ROUTINE TO COMPLETE OPEN OF 'D1:MEMORY'
449 1780 9D 44 03 STA ICBAL, X ; CALLING SUB SUPPLIES 'READ' OR 'WRITE'
450 1783 A9 17 LDA #.LOW.NAMEH ; IN ICAX1
451 1785 9D 45 03 STA ICBAH, X
452 1788 4C 56 E4 JMP CIO
453 ;
454 178B 8C 9A 17 ERRWR STY TEMP+1 ; TEMP STORE FOR Y FLAG

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 12

455	178E	20	AA	19	JSR	CLOSX	; CLOSE ##20
456	1791	A9	21		LDA	#. LOW. DELETE	; DELETE PART OF MENSAY
457	1793	9D	42	03	STA	ICCOM, X	
458	1796	20	79	17	JSR	OREST	
459	1799	A0	00		TEMP	LDY	#0 ; RESTORE FLAG
460	179B	60			RTS		; RETURN TO MAIN CALLER


```

461
462
463
464
465 179C 00 00 INISAV .DBYTE 0 ;DOSINI VECTOR SAVE LOC
466 179E 00 MEMFLG .BYTE 0
467 179F A2 00 MNDUP LDX #0
468 17A1 8E 9E 17 STX MEMFLG
469 17A4 8E 9F 15 STX LOADFG
470 17A7 CA DEX
471 17AB 86 08 STX WARMST
472 17AA 20 76 19 JSR INITIO
473
474 17AD 20 73 18 JSR MEMSVQ ;FIND OUT IF FILE D1:MEM.SAV EXISTS
475 17B0 10 06 BPL GOOD ;BRANCH IF MEM.SAV FILE EXISTS
476 17B2 A9 00 LDA #0
477 17B4 85 08 STA WARMST ;CLEAR WARM START FLAG
478 17B6 F0 3F BEQ FINAL
479
480
481 17B8 20 46 17 GOOD JSR MWRITE ;WRITE USER AREA TO MEM.SAV
482 17BB 30 05 BMI ERROR
483 17BD CE 9E 17 DEC MEMFLG ;SHOW MEMORY WRITTEN
484 17C0 30 35 BMI FINAL
485
486 17C2 A9 3A ERROR LDA #.LOW.ERRMES ;PRINT ERROR OCCURED MSG
487 17C4 A2 18 LDX #.HIGH.ERRMES
488 17C6 20 BE 19 JSR PRNTMSG ;GOTO MSG PRINTER
489
490 17C9 A9 5B LDA #.LOW.ERR ;PRINT QUERY TO RUN DOS
491 17CB A2 18 LDX #.HIGH.ERR
492 17CD 20 BE 19 JSR PRNTMSG ;GOTO MSG PRINTER
493
494
495
496 17D0 A9 05 LDA #GETREC
497 17D2 8D 42 03 STA ICCOM
498 17D5 A9 00 LDA #.LOW.STAKL
499 17D7 8D 44 03 STA ICBAL
500 17DA A9 01 LDA #.LOW.STAKH
501 17DC 8D 45 03 STA ICBALH
502 17DF A9 02 LDA #2
503 17E1 8D 48 03 STA ICBLL
504 17E4 A9 00 LDA #0
505 17E6 8D 49 03 STA ICBLLH
506 17E9 20 56 E4 JSR CID
507 17EC AD 00 01 LDA STAK ;SEE IF Y TYPED
508 17EF C9 59 CMP #'Y
509 17F1 D0 38 BNE RTCART ;BRANCH IF NOT
510 17F3 A9 00 LDA #0
511 17F5 85 08 STA WARMST
512
513 17F7 A2 20 FINAL LDX ##20
514 17F9 A9 0C LDA #CLOSE

```

```

515 17FB 9D 42 03          STA      ICCOM,X          ;SET UP CLOSE COMMAND
516 17FE 20 56 E4          JSR      CIO              ;PERFORM CLOSE COMMAND
517
518 1801 A5 0C          RRDUP LDA      DOSINI          ;SAVE DOS INIT VECTOR
519 1803 8D 9C 17          STA      INISAV
520 1806 A5 0D          LDA      DOSINI+1
521 1808 8D 9D 17          STA      INISAV+1
522
523 180B A9 40          LDA      #.LOW.DOS          ;SET UP DUP INIT ADDR AS
524 180D 85 0C          STA      DOSINI          ;DOS INIT VECTOR
525 180F A9 15          LDA      #.HIGH.DOS
526 1811 85 0D          STA      DOSINI+1
527
528 1813 A9 2F          RRDUP1 LDA     #.LOW.DUPSYS
529 1815 A2 10          LDX      ##10
530 1817 9D 44 03          STA      ICBAL,X
531 181A A9 18          LDA      #.HIGH.DUPSYS
532 181C 9D 45 03          STA      ICBAH,X
533 181F A0 00          LDY      #0
534 1821 8C 9E 15          STY      OPT              ;ASSURE NO /N OPTION IN EFFECT
535 1824 88            DEY              ;SHOW THAT DUP IS IN MEMORY
536 1825 8C 9D 15          STY      DUPFLG
537 1828 20 A4 15          JSR      SFLOAD          ;LOAD DUP.SYS AND RUN IT
538 182B 60            RTCART RTS
539 182C 45 3A 9B          EC      BYTE    'E: ',CR
540 182F            HILO    EC
541 0018          +ECH      =      EC/256
542 002C          +ECL      =      (-256)*ECH+EC
543 182F            HILO    MNDUP
544 0017          +MNDUPH    =      MNDUP/256
545 009F          +MNDUPL    =      (-256)*MNDUPH+MNDUP
546 182F 44 31 3A 44          DUPSYS  BYTE    'D1:DUP.SYS',CR
547 1833 55 50 2E 53
548 1837 59 53 9B
549
550 183A 45 52 52 4F          ERRMES .BYTE    'ERROR-SAVING USER MEMORY ON DISK',CR
551 183E 52 2D 53 41
552 1842 56 49 4E 47
553 1846 20 55 53 45
554 184A 52 20 4D 45
555 184E 4D 4F 52 59
556 1852 20 4F 4E 20
557 1856 44 49 53 4B
558 185A 9B
559 185B 54 59 50 45          ERR      .BYTE    'TYPE Y TO STILL RUN DOS',CR
560 185F 20 59 20 54
561 1863 4F 20 53 54
562 1867 49 4C 4C 20
563 186B 52 55 4E 20
564 186F 44 4F 53 9B

```

565

566

567

568

569

570

571

572

573 1873 20 B4 19

574 1876 A9 03

575 1878 9D 42 03

576 187B A9 3B

577 187D 9D 44 03

578 1880 A9 17

579 1882 9D 45 03

580 1885 A9 0C

581 1887 9D 4A 03

582 188A 20 56 E4

583 188D 08

584 188E 20 B4 19

585 1891 28

586 1892 60

587 1893

588

589

590

591

592 1893 A9 00

593 1895 F0 03

594 1897 20 39 19

595 189A A2 10

596 189C 20 56 E4

597 189F A9 00

598 18A1 F0 1A

599 18A3 EE A0 18

600 18A6 AD E2 02

601 18A9 8D E4 19

602 18AC AD E3 02

603 18AF 8D E5 19

604 18B2 A9 E2

605 18B4 AA

606 18B5 8D E0 19

607 18B8 A9 02

608 18BA 20 EF 18

609 18BD A9 00

610 18BF F0 1A

611 18C1 EE BE 18

612 18C4 AD E0 02

613 18C7 8D E4 19

614 18CA AD E1 02

615 18CD 8D E5 19

616 18D0 A9 E0

617 18D2 AA

618 18D3 8D E0 19

; **** SUBROUTINES FOR RESIDENT DUP ****

; ROUTINE TESTS IF MEM.SAV IS PRESENT ON THE DISK.

; RETURNS - MINUS IF NOT THERE

; PLUS IF MEM.SAV IS THERE

MEMSVG JSR CLOS20 ; CLOSE IOCB # 2

LDA #OPEN

STA ICCOM, X

LDA #.LOW.NAMEL

STA ICBAL, X

LDA #.LOW.NAMEH

STA ICBAL, X

LDA #ORDWRT

STA ICAX1, X ; TRY TO OPEN D1:MEM.SAV FOR READ/WRITE

JSR CIO

PHP ; SAVE STATUS

JSR CLOS20 ; CLOSE MEM.SAV

PLP ; RESTORE STATUS

RTS

; SAVE FILE SUBROUTINE - WRITE FILE BODY, INIT, & RUN VECTORS

WDR1 LDA #0 ; THIS IMMEDIATE VALUE MODIFIED

BEQ WDR2 ; BR IF MEM FILE DOESNT HAVE TO BE LOADED

JSR LDMEM

WDR2 LDX ##10

JSR CIO ; DO SAVE - WRITE BODY TO DISK

INITQ LDA #0 ; THIS IMMEDIATE VALUE CHANGED DURING SAVE

BEQ RUNG ; SET TO FF WHEN AN INIT VECTOR IS PRESENT

INC INITQ+1

LDA INITAD

STA VECTR ; IF INIT VECTOR FOR FILE SAVE IT

LDA INITAD+1

STA VECTR+1

LDA #.LOW.INITAD

TAX

STA LDST

LDA #.HIGH.INITAD

JSR WRVEC

RUNG LDA #0 ; THIS IMMEDIATE VALUE MODIFIED

BEQ NORNAD ; SET TO FF WHEN A RUN VECTOR IS PRESENT

INC RUNG+1

LDA RUNAD

STA VECTR ; IF RUN VECTOR FOR FILE SAVE IT

LDA RUNAD+1

STA VECTR+1

LDA #.LOW.RUNAD

TAX

STA LDST

```

619 18D6 A9 02          LDA      # HIGH.RUNAD
620 18D8 20 EF 18      JSR      WRVEC
621 18DB 20 AA 19      NORNAD   JSR      CLOSX      ; CLOSE IOCBS 1 & 2
622 18DE AD 9E 17      LDA      MEMFLG
623 18E1 2D 94 18      AND      WDR1+1
624 18E4 F0 06         BEQ      DRRDUP
625 18E6 EE 94 18      INC      WDR1+1      ; RESET MEM. NEEDS TO BE LOADED FLAG
626 18E9 4C 13 18      JMP      RRDUP1      ; RELOAD & RUN DUP
627 18EC 4C 75 20      DRRDUP   JMP      DOSOS      ; RUN THE SWAPPED IN DUP
628
629
630
631 18EF 8D E1 19      WRVEC    STA      LDST+1
632 18F2 EB           INX
633 18F3 8E E2 19      STX      LDND
634 18F6 8D E3 19      STA      LDND+1
635 18F9 A2 10         LDX      #$10
636 18FB A9 E0         LDA      # LOW.LDST
637 18FD 9D 44 03      STA      ICBAL,X
638 1900 A9 19         LDA      # HIGH.LDST
639 1902 9D 45 03      STA      ICBAL,X
640 1905 A9 06         LDA      #6
641 1907 9D 48 03      STA      ICBLL,X
642 190A A9 00         LDA      #0
643 190C 9D 49 03      STA      ICBLL,X
644 190F 4C 56 E4      JMP      CIO      ; WRITE INIT OR RUN ADDRESS
645
646
647          JUMP TO CARTRIDGE
648
649 1912 20 39 19      CLMJMP   JSR      LDMEM
650 1915 A9 00         LDA      #0      ; SHOW DUP NO LONGER IN MEMORY
651 1917 8D 9D 15      STA      DUPFLG
652 191A 20 2E 19      JSR      RELDIN      ; RESTORE DOS INIT VECTOR SAVED
653 191D 6C FA BF      JMP      (CARTST)      ; JUMP TO CARTRIDGE
654
655
656          LOAD MEM.SAV (IF IT EXISTS) BEFORE RUN AT ADDRESS
657
658 1920 20 39 19      LMTR     JSR      LDMEM      ; LOAD MEM.SAVE IF IT EXISTS
659 1923 A9 00         LDA      #0      ; SHOW THAT DUP NO LONGER IN MEMORY
660 1925 8D 9D 15      STA      DUPFLG
661 1928 20 2E 19      JSR      RELDIN      ; RESTORE DOS INIT VECTOR SAVED
662 192B 6C 1A 00      JMP      (RAMLO)      ; RUN AT ADDRESS
663
664          RESTORE DOSINI VECTOR FROM SAVED LOCATION
665
666 192E AD 9C 17      RELDIN   LDA      INISAV
667 1931 85 0C         STA      DOSINI
668 1933 AD 9D 17      LDA      INISAV+1
669 1936 85 0D         STA      DOSINI+1
670 1938 60           RTS
671
672

```

```

673      ; SUBROUTINE - LDMEM
674      ; LOAD MEM.SAV IF IT EXISTS
675      ;
676 1939 AD 9E 17 LDMEM LDA MEMFLG
677 193C D0 01      BNE LDMEM1      ; BRANCH IF MEMORY WAS SAVED
678 193E 60      RTS
679 193F 20 73 18 LDMEM1 JSR MEMSVQ
680 1942 10 06      BPL LDMEM2      ; BRANCH IF MEM.SAV FILE DOES EXIST
681 1944 A9 00      LDA #0          ; TELL CART PGM AREA Clobbered
682 1946 85 08      STA WARMST
683 1948 F0 24      BEQ CLOS2       ; GO CLOSE AND GOTO CART
684      ;
685 194A A9 03 LDMEM2 LDA #OPEN
686 194C 9D 42 03  STA ICCOM, X
687 194F 20 56 E4  JSR CIO          ; REOPEN MEM.SAV
688 1952 A9 07      LDA #GETCHR
689 1954 9D 42 03  STA ICCOM, X
690 1957 A9 8A      LDA #.LOW.MLENL+1
691 1959 9D 48 03  STA ICBLL, X
692 195C A9 15      LDA #.LOW.MLENH
693 195E 9D 49 03  STA ICBLH, X
694 1961 A9 7C      LDA #.LOW.NDOSL
695 1963 9D 44 03  STA ICBAL, X
696 1966 A9 1D      LDA #.LOW.NDOSL
697 1968 9D 45 03  STA ICBAL, X
698 196B 20 56 E4  JSR CIO
699 196E A9 0C CLOS2 LDA #CLOSE
700 1970 9D 42 03  STA ICCOM, X
701 1973 4C 56 E4  JMP CIO          ; CLOSE MEM.SAV
702      ;
703      ; CLOSE ALL IOCBs & RE-OPEN ZERO AS SCREEN EDITOR
704      ;
705 1976 20 6E E4 INITIO JSR CIOINV      ; THIS ROUTINE CLOSES ALL IOCB'S
706      ; THEN REOPENS THE SCREEN EDITOR
707 1979 A2 00      LDX #0
708 197B A9 03      LDA #OPEN
709 197D 9D 42 03  STA ICCOM, X
710 1980 A9 2C      LDA #.LOW.ECL
711 1982 9D 44 03  STA ICBAL, X
712 1985 A9 18      LDA #.LOW.ECH
713 1987 9D 45 03  STA ICBAL, X
714 198A A9 0C      LDA #ORDWRT
715 198C 9D 4A 03  STA ICAX1, X
716 198F 20 56 E4  JSR CIO
717      ;
718 1992 A2 00      LDX #0          ; DELAY UNTIL DMA (SCREEN) IS RESTORED
719 1994 8E 1C 02  STX CDTMV3      ; CLEAR TIMER NUMBER 3
720 1997 8E 1D 02  STX CDTMV3+1
721 199A A0 01      LDY #1          ; WAIT FOR ONE VBLANK
722 199C A9 03      LDA #3          ; USE TIMER # 3
723 199E 8D 2A 02  STA CDTMF3      ; SET TIMER DONE FLAG TO NOT DONE
724 19A1 20 5C E4  JSR SETVBV      ; SYSTEM CALL TO SET TIMER
725 19A4 AD 2A 02  LDA CDTMF3      ; WAIT UNTIL TIMER IS DONE
726 19A7 D0 FB      BNE WAITIM

```

```

727
728 19A9 60
729
730
731
732 19AA A9 0C
733 19AC A2 10
734 19AE 9D 42 03
735 19B1 20 56 E4
736
737
738
739 19B4 A2 20
740 19B6 A9 0C
741 19B8 9D 42 03
742 19BB 4C 56 E4
743
744
745
746
747
748
749
750
751
752
753 19BE 8D 44 03
754 19C1 8E 45 03
755
756
757
758 19C4 A9 80
759 19C6 8D 48 03
760 19C9 A2 00
761 19CB 8E 49 03
762 19CE A9 09
763 19D0 8D 42 03
764
765
766
767
768 19D3 AD 9D 15
769 19D6 D0 03
770
771 19D8 4C 56 E4
772
773 19DB 4C AA 31
774
775
776 19DE FF FF
777 19E0
778 0019
779 00DE
780 19E0

RTS

CLOSX - CLOSE IOCBS 10,20
CLOSX LDA #CLOSE
LDX ##10
STA ICCOM, X
JSR CIO

ENTRY TO CLOSE IOCB # 2 ONLY
CLOS20 LDX ##20
LDA #CLOSE
STA ICCOM, X
JMP CIO

SUBROUTINE - PRNTMSG
PUTS A CHARACTER STRING TERMINATED BY A CARRIAGE RETURN CHAR TO
SCREEN EDITOR.

ENTRY - REG A : LOW BYTE MSG ADDRESS
REG X : HI BYTE MSG ADDRESS

PUT PARAMS IN IOCB - USE IOCB 0 FOR SCREEN EDITOR
PRNTMSG STA ICBAL ;SET MSG ADDR IN IOCB BUFF ADDR
STX ICBAH

SET UP REST OF IOCB
LDA ##80 ;SET IN BUFFER LENGTH
STA ICBLL ;ASSUME 128 BYTES MAX
LDX #0 ;USE REG X TO SET IN IOCB INDEX FOR CIO
STX ICBLLH
LDA #PUTREC ;PUT MSG
STA ICCOM

TEST IF DUP IS RESIDENT - IF IS THEN USE INDIRECT CIO ROUTINE
TO TEST FOR BREAK KEY ABORT
LDA DUPFLG ;=ZERO IF NON-RESIDENT DUP NOT IN MEM
BNE INMEM ;IN MEMORY THEN USE INDIRECT CIO CALL

JMP CIO ;ELSE GO DIRECT TO CIO & RETURN

INMEM JMP CIO1 ;USE CIO CALL WITH TEST FOR BREAK KEY AB

SAVH .BYTE $FF, $FF
HILO SAVH
+SAVHH = SAVH/256
+SAVHL = (-256)*SAVHH+SAVH
LDST: .RES 2

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 19

781 19E2
782 0019
783 00E0
784 19E2
785 19E4

	HILD	LDST
+LDSTH	=	LDST/256
+LDSTL	=	(-256)*LDSTH+LDST
LDND:	RES	2
VECTR:	RES	2

```
786 . PAGE
787 ; **** SIO INTERRUPT SERVICE ROUTINES ****
788 ;
789 ;
790 ; EQUATES FOR INTERRUPT ROUTINES MOVED FROM SIO
791 ;
792 ; ZERO PAGE
793 ;
794 0032 BUFRLO = $32 ; POINTER TO BYTE TO SEND OR RECEIVE
795 0033 BUFRHI = $33
796 0034 BFENLO = $34 ; POINTER TO BYTE AFTER END OF BUFFER
797 0035 BFENHI = $35
798 0031 CHKSUM = $31 ; LOC TO STORE DATA FRAME CHECKSUM
799 003B CHKSNL = $3B ; CHECKSUM SENT FLAG- =FF SENT
800 003C NOCKSM = $3C ; FLAG NO CHECK SUM TO BE RECEIVED-NOT ZE
801 0030 STATUS = $30 ; HOLD FOR STATUS TO BE PUT IN DCB
802 0038 BUFRFL = $38 ; FLAG-IF FF RECEIVE BUFFER IS FULL
803 0039 RECVDN = $39 ; FLAG RECEIVE NOT DONE. USED BY WAIT LOO
804 0010 POKMSK = $10 ; POKEY INTERRUPT MASK SHADOW FOR IRQEN
805 ;
806 ; HARDWARE REGISTERS USED IN SIO INTERRUPT ROUTINES
807 ;
808 D20A SKRES = $D20A ; SERIAL PORT STATUS RESET ON POKEY
809 D20D SEROUT = $D20D ; SERIAL OUTPUT REGISTER
810 D20D SERIN = SEROUT ; SERIAL PORT INPUT REG ON POKEY
811 D20E IRQEN = $D20E ; IRQ INTERRUPT ENABLE ON POKEY
812 D20F SKSTAT = $D20F ; SERIAL PORT STATUS REG ON POKEY
813 ;
814 ; ERROR CODES RETURNED BY SIO
815 ;
816 008C FRMERR = $8C ; FRAMING ERROR ON INPUT
817 008E OVRRUN = $8E ; DATA FRAME OVER RUN-BIT D5 IN SKSTAT
818 008F CHKERR = $8F ; DATA FRAME CHECKSUM ERROR
```



```

819
820
821
822
823
824
825
826
827
828
829
830
831
832
833
834 19E6 98
835 19E7 48
836
837 19E8 E6 32
838 19EA D0 02
839 19EC E6 33
840
841
842
843 19EE A5 32
844 19F0 C5 34
845 19F2 A5 33
846 19F4 E5 35
847 19F6 90 1A
848
849 19F8 A5 3B
850 19FA D0 09
851
852
853
854 19FC A5 31
855 19FE 8D 0D D2
856 1A01 C6 3B
857 1A03 D0 09
858
859
860
861
862 1A05 A5 10
863 1A07 09 08
864 1A09 85 10
865 1A0B 8D 0E D2
866
867
868
869 1A0E 68
870 1A0F A8
871 1A10 68
872 1A11 40

```

PAGE
 **** INTERRUPT SERVICE ROUTINE TO OUTPUT DATA NEEDED ****
 ;
 ;
 ;
 ;
 ; IT UPDATES THE BYTE TO PUT ON SERIAL I/O BUS POINTER
 ; UNTIL END OF BUFFER. AFTER EACH UPDATE OF THE PTR ADDS THE
 ; VALUE OF THE BYTE TO THE CHECKSUM. OUTPUTS THE CHECKSUM WHEN
 ; PTR EQUALS THE END OF BUFFER PTR (POINTS TO BYTE AFTER BUFFER).
 ; RETURNS TO THIS ROUTINE AFTER CHECKSUM PASSED AND RESETS POKEY
 ; INTERRUPT REG TO HAVE THE TRANSMIT DONE ROUTINE CALLED TO END
 ; WAIT LOOP (SEE SIO LISTING).
 ;
 ; K. B. 6/10/80
 ;
 ISRODN TYA ; SAVE Y REG ON STACK
 PHA
 ;
 ;
 INC BUFRLO
 BNE NOWRPO ; INCREMENT PTR TO NEXT BYTE
 INC BUFRHI ; TO SEND
 ;
 ; PATCH TO ROUTINE - CHANGED CHECK
 ;
 NOWRPO LDA BUFRLO ; CHECK IF PTR IS WITHIN BUFFER
 CMP BFENLO ; DO A DOUBLE PRECISION SUBTRACT
 LDA BUFRHI
 SBC BFENHI
 BCC NOTEND ; BRANCH IF (BUFR) < (BFEN)--MORE TO SEND
 ;
 ;
 LDA CHKSNT ; TEST IF CHECKSUM ALREADY SENT
 BNE RELONE ; BRANCH IF ALREADY SENT
 ;
 ; SEND CHECKSUM AND SET FLAG
 ;
 ;
 LDA CHKSUM
 STA SEROUT ; PUT CHECKSUM IN SERIAL OUT REG
 DEC CHKSNT ; SET FLAG TO FF HEX
 BNE CHKDON ; RETURN
 ;
 ; AFTER CHECKSUM SENT AND CAUSE NEXT INTERRUPT THEN CHANGE POKEY
 ; MASK TO ENABLE TRANSMIT DONE INTERRUPT AND TERMINATE WAIT LOOP.
 ;
 ;
 RELONE LDA POKMSK ; GET POKEY MASK
 ORA #\$08 ; OR IN ENABLE
 STA POKMSK
 STA IRQEN ; ENABLE THE INTERRUPTS
 ;
 ; RESTORE REGS AND RETURN
 ;
 CHKDON PLA
 TAY ; RESTORE Y REG
 PLA ; RESTORE A REG SAVED IN OS IRQ INTERRUPT
 RTI

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 22

873

874

875

876 1A12 A0 00

877 1A14 B1 32

878 1A16 8D 0D D2

879

880 1A19 18

881 1A1A 65 31

882 1A1C 69 00

883 1A1E 85 31

884

885 1A20 4C 0E 1A

886

887

MORE TO SEND. SEND NEXT BYTE POINTED AT BY BUFR.

NOTEND

LDY #0

LDA (BUFRLO),Y

STA SEROUT

CLC

ADC CHKSUM

ADC #0

STA CHKSUM

JMP CHKDON

***** END OF OUT SERVICE ROUTINE *****

;GET NEXT BYTE

;PUT IN SERIAL OUT REG

;ADD BYTE TO CHECKSUM

;GO RETURN AND WAIT FOR NEXT BYTE

```

888
889
890
891
892
893
894
895
896
897
898
899
900
901
902
903
904
905 1A23 98
906 1A24 4B
907
908
909
910 1A25 AD 0F D2
911 1A2B BD 0A D2
912
913
914
915 1A2B 30 04
916 1A2D A0 8C
917 1A2F 84 30
918
919 1A31 29 20
920 1A33 D0 04
921 1A35 A0 8E
922 1A37 84 30
923
924
925
926
927 1A39 A5 38
928 1A3B F0 13
929 1A3D AD 0D D2
930 1A40 C5 31
931 1A42 F0 04
932 1A44 A0 8F
933 1A46 84 30
934
935
936
937 1A48 A9 FF
938 1A4A 85 39
939
940
941

```

PAGE
 **** SERIAL INPUT READY INTERRUPT SERVICE ROUTINE ****
 AFTER SERIAL RECEIVE IS ENABLED ROUTINE IS USED TO COLLECT
 BYTES FROM THE SERIAL INPUT REG AND PUT THEM IN BUFFER.
 WILL STOP WHEN BUFFER IS FULL. IF A CHECKSUM IS EXPECTED
 ROUTINE WILL MARK BUFFER FULL AND CONTINUE. WHEN CHECKSUM
 RECEIVED IT WILL CHECK IF = TO CHECKSUM IT WAS MAKING.
 WILL STORE ERRORS FOUND IN STATUS LOCATION.
 THE IRQ INTERRUPT HANDLER IN THE OS PUSHES THE USER'S A REGISTER
 ONTO THE STACK BEFORE CALLING THIS ROUTINE.
 K. B. 6/11/80
 ISRSIR TYA ;SAVE Y REG ON STACK
 PHA
 GET STATUS FROM POKEY THEN RESET IT.
 LDA SKSTAT
 STA SKRES ;IGNORES VALUE- JUST STROBED
 CHECK FOR ERRORS
 BMI NTFRAM ;BIT 8 SET IF NO FRAMING ERROR
 LDY #FRMERR
 STY STATUS ;SET FRAME ERROR STATUS
 NTFRAM AND ##20 ;IF BIT 5 CLEAR THEN FRAME OVER RUN
 BNE NTOVRN ;BRANCH IF NO OVER RUN
 LDY #OVRN
 STY STATUS ;ELSE SET OVERRUN ERROR STATUS
 CHECK IF BUFFER FULL AND THIS IS A CHECKSUM. IF IT IS, THEN
 CHECK IF DATA SENT WAS VALID.
 NTOVRN LDA BUFRFL ;TEST FOR BUFFER FULL (NOT ZERO)
 BEQ NOTYET ;IF ZERO THEN NOT YET, THIS IS DATA.
 LDA SERIN ;ELSE THIS IS CHECKSUM
 CMP CHKSUM ;ARE THEY EQUAL?
 BEQ SRETRN ;YES, THEN RETURN
 LDY #CHKERR ;ELSE SET CHECK SUM ERROR STATUS
 STY STATUS
 SET RECEIVE DONE TO END WAIT LOOP
 SRETRN LDA ##FF ;DONE VALUE
 STA RECVDN
 RESTORE REGS AND RETURN

```

942 1A4C 68
943 1A4D A8
944 1A4E 68
945 1A4F 40
946
947
948
949
950 1A50 AD 0D D2
951 1A53 A0 00
952 1A55 91 32
953
954 1A57 18
955 1A58 65 31
956 1A5A 69 00
957 1A5C 85 31
958
959 1A5E E6 32
960 1A60 D0 02
961 1A62 E6 33
962
963
964
965 1A64 A5 32
966 1A66 C5 34
967 1A68 A5 33
968 1A6A E5 35
969 1A6C 90 DE
970
971
972
973 1A6E A5 3C
974 1A70 F0 06
975
976 1A72 A9 00
977 1A74 85 3C
978 1A76 F0 D0
979
980
981
982 1A78 C6 38
983 1A7A D0 D0
984
985
986 1A7C
987 1A7C
988 001A
989 007C
990
991 070C 7C 1A
992
993 0100
994 070E
995 0001

SUSUAL PLA
TAY
PLA
RTI
; RESTORE Y REG
; RESTORE A REG

;
; IF BYTE IS DATA, THEN GET HERE. PUT BYTE IN BUFFER AND CHECK IF
; AT END OF BUFFER.
;
NOTYET LDA SERIN ; GET DATA BYTE
LDY #0
STA (BUFRLO),Y ; STORE IT IN THE BUFFER
;
CLC
ADC CHKSUM ; ADD DATA BYTE TO CHECKSUM
ADC #0
STA CHKSUM
;
INC BUFRLO ; INCREMENT POINTER TO LOCATION
BNE NTWRP1 ; FOR NEXT BYTE INPUT
INC BUFRHI
;
; THE PATCH CHANGED THE TEST FOR END OF BUFFER
;
NTWRP1 LDA BUFRLO ; DO DOUBLE PRECISION SUBTRACT
CMP BFENLO
LDA BUFRHI
SBC BFENHI ; CARRY CLEAR IF BORROW
BCC SUSUAL ; BRANCH IF (BUFR) < (BFEN)--WITHIN BUFFER
;
; DONE WITH DATA. SEE IF CHECKSUM TO BE SENT
;
LDA NOCKSM ; IF = ZERO THEN A CHECKSUM
BEQ GOON ; WILL FOLLOW THE DATA
;
LDA #0 ; ELSE NO CHECKSUM TO FOLLOW
STA NOCKSM ; CLEAR NO CHECKSUM FLAG
BEQ SRETRN ; RETURN AFTER SET RECEIVE DONE FLAG
;
; SET BUFFER FULL AND THEN GO GET CHECKSUM
;
GOON DEC BUFRFL ; SET BUFFER FULL FLAG TO FF
BNE SUSUAL ; GO RETURN
;
***** END OF RECEIVE SERIAL INPUT INTERRUPT ROUTINE *****
MDEND = *
HILO MDEND
+MDENDH = MDEND/256
+MDENDL = (-256)*MDENDH+MDEND
*= $70C
; BYTE MDENDL, MDENDH ; SET END ADDR IN FMS PAST RES DUP SO
; BUFFERS DON'T CLOBBER IT.
;
STAK = $100
HILO STAK
+STAKH = STAK/256

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 25

996 0000

+STAKL = (-256)*STAKH+STAK

```

997
998
999
1000
1001 1D7C
1002 070E
1003 001D
1004 007C
1005
1006 1D7C
1007 1D7C
1008 001D
1009 007C
1010 1DA4
1011 001D
1012 00A4
1013 1DF4
1014 1E74
1015 1DF1
1016 1EF4
1017 001D
1018 00F4
1019 1EF4
1020 001E
1021 0074
1022 1EF4
1023 001D
1024 00F1
1025 0000
1026 0001
1027 00FA
1028 0000
1029 1EF4
1030 1EF5
1031 1EF6
1032 1EF7
1033 1EF8
1034 1EF9
1035 1EFE
1036 1EFF
1037 1F00
1038 1F01
1039 1F02
1040 1F03
1041 1F04
1042 1F04
1043 1F06
1044 1F06
1045 1F08
1046 1F0A
1047 1F0B
1048 1F0B
1049 1F0C
1050 1F0C

```

```

PAGE
***** BEGINNING OF NON-RESIDENT PORTION OF DUP *****
;
;
NDOS = MDEND+$300 ; END OF THE SYSTEM BUFFERS AND MINIDUP
HILO NDOS
+NDOSH = NDOS/256
+NDOSL = (-256)*NDOSH+NDOS
*= NDOS

PAR: .RES 40 ; PARAMETER AREA
PARH = PAR/256
PARL = (-256)*PARH+PAR
LINE: .RES 80 ; TYPE IN LINE BUFFER
LBUFH = LINE/256
LBUFL = (-256)*LBUFH+LINE
DBUF: .RES $100 ; DATA BUFFER FOR COPY
DB1 = DBUF+$80
DB3 = DBUF-3
HILO DBUF
+DBUFH = DBUF/256
+DBUFL = (-256)*DBUFH+DBUF
HILO DB1
+DB1H = DB1/256
+DB1L = (-256)*DB1H+DB1
HILO DB3
+DB3H = DB3/256
+DB3L = (-256)*DB3H+DB3
DBLL = 0
DBLH = 1 ; DATA BUFFER LENGTH=$100
EDBLL = $FA ; DATA BUFFER LENGTH USED IN USEPGM
EDBLH = 0 ; MUST BE A MULTIPLE OF 125, SECTOR DATA
MENUSZ: .RES 1
PER: .RES 1
UNNO: .RES 1
RCNT: .RES 1
SSTAT: .RES 1
SWDP: .RES 5
CSRC: .RES 1
CDES: .RES 1
SAVX: .RES 1
PTR: .RES 1
IPTR: .RES 1
CTR: .RES 1
T1: .RES 2
BUFLEN = T1 ; SAVE AREA FOR BUFR LEN, USED IN USEPGM
STVEC: .RES 2 ; A TEMP OF SOME KIND
MLT125 = STVEC ; TEMP STORE FOR MULTIPLE OF 125, USEPGM
SECSIZ: .RES 2 ; TO STORE SECT SIZE IN BYTES FOR DUP DSK
EOFFLG: .RES 1 ; ENDFILE FLAG FOR SOURCE IN DUPFIL
FTRF: .RES 1 ; FIRST TIME READ FLAG USED IN DUPFIL
TWODRV = FTRF ; FLAG TO SHOW IF 1 OR 2 DRIVES. USED IN
DTH =*
HILO DTH

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 27

1051 001F

1052 000C

1053 1F0C 45 3A 9B

1054 001F

1055 000C

+DTHH = DTH/256

+DTHL = (-256)*DTHH+DTH

EDN BYTE 'E', CR

EDH = EDN/256

EDL = (-256)*EDH+EDN

1056

1057

1058

1059

1060 1F0F 7D

1061 1F10 44 49 53 48

1062 1F14 20 4F 50 45

1063 1F18 52 41 54 49

1064 1F1C 4E 47 20 53

1065 1F20 59 53 54 45

1066 1F24 4D 20 49 49

1067 1F28 20 56 45 52

1068 1F2C 53 49 4F 4E

1069 1F30 20 32 2E 30

1070 1F34 53 9B

1071 1F36 43 4F 50 59

1072 1F3A 52 49 47 48

1073 1F3E 54 20 31 39

1074 1F42 38 30 20 41

1075 1F46 54 41 52 49

1076 1F4A 9B 9B

1077 1F4C 41 2E 20 44

1078 1F50 49 53 4B 20

1079 1F54 44 49 52 45

1080 1F58 43 54 4F 52

1081 1F5C 59 20 49 2E

1082 1F60 20 46 4F 52

1083 1F64 4D 41 54 20

1084 1F68 44 49 53 4B

1085 1F6C 9B

1086 1F6D 42 2E 20 52

1087 1F71 55 4E 20 43

1088 1F75 41 52 54 52

1089 1F79 49 44 47 45

1090 1F7D 20 20 4A 2E

1091 1F81 20 44 55 50

1092 1F85 4C 49 43 41

1093 1F89 54 45 20 44

1094 1F8D 49 53 4B 9B

PAGE

**** DQS MENU ****

DMENU

. BYTE CLSCR

. BYTE 'DISK OPERATING SYSTEM II VERSION 2.05',CR

. BYTE 'COPYRIGHT 1980 ATARI',CR,CR

. BYTE 'A. DISK DIRECTORY I. FORMAT DISK',CR

. BYTE 'B. RUN CARTRIDGE J. DUPLICATE DISK',CR

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 29

1095

1096 1F91 43 2E 20 43

1097 1F95 4F 50 59 20

1098 1F99 46 49 4C 45

1099 1F9D 20 20 20 20

1100 1FA1 20 20 4B 2E

1101 1FA5 20 42 49 4E

1102 1FA9 41 52 59 20

1103 1FAD 53 41 56 45

1104 1FB1 9B

1105 1FB2 44 2E 20 44

1106 1FB6 45 4C 45 54

1107 1FBA 45 20 46 49

1108 1FBE 4C 45 28 53

1109 1FC2 29 20 4C 2E

1110 1FC6 20 42 49 4E

1111 1FCA 41 52 59 20

1112 1FCE 4C 4F 41 44

1113 1FD2 9B

1114 1FD3 45 2E 20 52

1115 1FD7 45 4E 41 4D

1116 1FDB 45 20 46 49

1117 1FDF 4C 45 20 20

1118 1FE3 20 20 4D 2E

1119 1FE7 20 52 55 4E

1120 1FEB 20 41 54 20

1121 1FEF 41 44 44 52

1122 1FF3 45 53 53 9B

1123 1FF7 46 2E 20 4C

1124 1FFB 4F 43 4B 20

1125 1FFF 46 49 4C 45

1126 2003 20 20 20 20

1127 2007 20 20 4E 2E

1128 200B 20 43 52 45

1129 200F 41 54 45 20

1130 2013 4D 45 4D 2E

1131 2017 53 41 56 9B

. BYTE 'C. COPY FILE K. BINARY SAVE', CR

. BYTE 'D. DELETE FILE(S) L. BINARY LOAD', CR

. BYTE 'E. RENAME FILE M. RUN AT ADDRESS', CR

. BYTE 'F. LOCK FILE N. CREATE MEM. SAV', CR

```

1132
1133 201B 47 2E 20 55      .BYTE  'G. UNLOCK FILE  O. DUPLICATE FILE',CR
1134 201F 4E 4C 4F 43
1135 2023 4B 20 46 49
1136 2027 4C 45 20 20
1137 202B 20 20 4F 2E
1138 202F 20 44 55 50
1139 2033 4C 49 43 41
1140 2037 54 45 20 46
1141 203B 49 4C 45 9B
1142 203F 48 2E 20 57      .BYTE  'H. WRITE DOS FILES',CR
1143 2043 52 49 54 45
1144 2047 20 44 4F 53
1145 204B 20 46 49 4C
1146 204F 45 53 9B
1147 2052 1D 1D 1D 1D      .BYTE  CDN, CDN, CDN, CDN, CDN
1148 2056 1D
1149 2057
1150 0148      DMEND  ==
1151 2057      DULEN  =      DMEND-DMENU
1152 0001      HILO   DULEN
1153 0048      +DULENH =      DULEN/256
1154 2057      +DULENL =      (-256)*DULENH+DULEN
1155 001F      HILO   DMENU
1156 000F      +DMENUH =      DMENU/256
1157          +DMENUL =      (-256)*DMENUH+DMENU
1158 2057 39 21 EE 26      DUJPT .WORD  DIRLST, STCAR, CPYFIL, DELFIL, RENFIL, LKFIL, ULFIL
1159 205B 78 23 C9 21      A      B      C      D      E      F      G
1160 205F 37 26 70 29
1161 2063 98 29
1162 2065 D9 27 80 26      .WORD  WBOOT, FMDSK, DUPDSK, SAVFIL, LDFIL, BRUN, MEMSAV
1163 2069 58 2A 2E 2F      H      I      J      K      L      M      N
1164 206D 1A 29 4C 27
1165 2071 9A 27
1166 2073 1E 2D          O
1167 2075          .WORD  DUFFIL
1168 0020          HILO   DUJPT
1169 0057      +DUJPTH =      DUJPT/256
1170 000F      +DUJPTL =      (-256)*DUJPTH+DUJPT
          DUNUM  =      15      ;NUMBER OF FUNCTIONS

```

```

1171      PAGE
1172      ; **** DISK OPERATING SYS MONITOR ****
1173      ;
1174      ;
1175      2075 A2 FF      DOSOS LDX      #$FF
1176      2077          HILO    DOSOS
1177      0020      +DOSOSH =      DOSOS/256
1178      0075      +DOSOSL =      (-256)*DOSOSH+DOSOS
1179      2077 D8          CLD          ; MAKE SURE DECIMAL MODE OFF
1180      2078 86 11      STX      BRKKEY
1181      207A E8          INX
1182      207B 8E 9F 15   STX      LOADFG
1183      207E A9 02      LDA      #2
1184      2080 85 52      STA      LMARGN
1185      2082 A9 27      LDA      #39
1186      2084 85 53      STA      RMARGN      ; SET MARGINS
1187      2086 A5 10      LDA      POKMSK      ; ENABLE BREAK INTERRUPTS
1188      2088 09 80      ORA      #$80
1189      208A 85 10      STA      POKMSK
1190      208C 8D 0E D2   STA      IRGEN
1191      20BF 20 76 19   JSR      INITIO      ; CLOSE FILES
1192      ;
1193      ; DISK UTILITY MONITOR
1194      ;
1195      2092      DSKUTL
1196      2092 A9 0F      DU1  LDA      #DUNUM
1197      2094 8D F4 1E   STA      MENUSZ      ; SET MENU SIZE
1198      2097 A9 57      LDA      #.LOW.DUJPTL
1199      2099 85 18      STA      JMPTBL
1200      209B A9 20      LDA      #.LOW.DUJPTH
1201      209D 85 19      STA      JMPTBL+1    ; SET UP JUMP TABLE ADDRESS
1202      ; FALL THRU TO MENU SELECT
1203      ;
1204      ;
1205      ;
1206      ; MENU SELECT MONITOR --- VECTORS TO ROUTINE SELECTED FROM MENU.
1207      ;
1208      209F A9 0F      SHMEN LDA      #.LOW.DMENUL    ; GET MENU ADDRESS
1209      20A1 8D 44 03   STA      ICBAL
1210      20A4 A9 1F      LDA      #.LOW.DMENUH
1211      20A6 8D 45 03   STA      ICBAH
1212      20A9 A9 48      LDA      #.LOW.DULENL    ; GET MENU LENGTH
1213      20AB 8D 48 03   STA      ICBLH
1214      20AE A9 01      LDA      #.LOW.DULENH
1215      20B0 8D 49 03   STA      ICBLH
1216      20B3 20 A3 31   JSR      DSPMSG      ; SHOW MENU
1217      ;
1218      ; SELECT ITEM FROM MENU

```


ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 33

1267
1268 210D 4E 4F 20 53
1269 2111 55 43 48 20
1270 2115 49 54 45 4D
1271 2119 9B
1272
1273
1274
1275 211A 53 45 4C 45
1276 211E 43 54 20 49
1277 2122 54 45 4D 20
1278 2126 4F 52 20 D2
1279 212A C5 D4 D5 D2
1280 212E CE
1281 212F 20 46 4F 52
1282 2133 20 4D 45 4E
1283 2137 55 9B
1284 2139
1285 0021
1286 000D
1287 2139
1288 0021
1289 001A
1290 2086
1291 2139
1292 0020
1293 0086

NSI .PAGE
NSI .BYTE 'NO SUCH ITEM', CR

; PROMPT FOR MENU SELECTION OR REDISPLAY MENU - RETURN IS IN INVERSE

SIT .BYTE 'SELECT ITEM OR ', \$D2, \$C5, \$D4, \$D5, \$D2, \$CE

.BYTE ' FOR MENU', CR

HILO NSI
+NSIH = NSI/256
+NSIL = (-256)*NSIH+NSI
HILO SIT
+SITH = SIT/256
+SITL = (-256)*SITH+SIT
MNSL = MENUSL
HILO MNSL
+MNSLH = MNSL/256
+MNSLL = (-256)*MNSLH+MNSL

1294

1295

1296

1297

1298 2139 A7 21

1299 213B 20 CF 30

1300 213E 20 C4 2E

1301 2141 AE 01 1F

1302 2144 A9 9B

1303 2146 9D 7B 1D

1304 2149 BD 7A 1D

1305 214C C9 3A

1306 214E D0 1B

1307 2150 A9 2A

1308 2152 9D 7B 1D

1309 2155 9D 7D 1D

1310 2158 A9 2E

1311 215A 9D 7C 1D

1312 215D A9 9B

1313 215F 9D 7E 1D

1314 2162 E8

1315 2163 E8

1316 2164 E8

1317 2165 8E 01 1F

1318 2168 8E 00 1F

1319 216B A2 20

1320 216D 20 DD 31

1321 2170 20 E8 30

1322 2173 20 C4 30

1323 2176 A9 06

1324 2178 A2 10

1325 217A 9D 4A 03

1326 217D A9 03

1327 217F 9D 42 03

1328 2182 8E FE 1E

1329 2185 E0 10

1330 2187 D0 01

1331 2189 20 EE 31

1332 218C AD 01 1F

1333 218F 38

1334 2190 ED 00 1F

1335 2193 C9 03

1336 2195 F0 03

1337 2197 4C 5E 25

1338 219A AE 00 1F

1339 219D BD 7C 1D

1340 21A0 C9 44

1341 21A2 D0 F3

1342 21A4 4C 6C 25

PAGE

**** DIRECTORY LISTING ROUTINE ****

DIRLST

WORD

DLMG

JSR GETIC1

JSR USEBUF

LDX PTR

LDA #CR

STA PAR-1,X

LDA PAR-2,X

CMP #'

BNE GLF

LDA #'*

STA PAR-1,X

STA PAR+1,X

LDA #'

STA PAR,X

LDA #CR

STA PAR+2,X

INX

INX

INX

STX PTR

STX SAVX

LDX ##20

JSR PIOCB

JSR GETFIL

JSR PERX

LDA #6

LDX ##10

STA ICAX1,X

LDA #OPEN

STA ICCOM,X

STX CSRC

CPX ##10

BNE **3

JSR CIOCL

LDA PTR

SEC

SBC SAVX

CMP #3

BEQ DLST1

JMP PDES

LDX SAVX

LDA PAR,X

CMP #'D

BNE DLST0

JMP PDES1

INIT BUFADR & BUFLN

ASSURE GOOD TERM

LAST CHAR OF SEARCH SPEC

IF COLON, ADD *.*

READ DIR INFO

OPEN

COPY SOURCE=DIRECTORY INFO

IF ONLY 3 CHARS, IS 'D:'CR, USE DEFAULT

GO INTO COPY

GO INTO COPY WITH DES='E:'

GLF

DLST0

DLST1

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 35

1343
1344 21A7 44 49 52 45
1345 21AB 43 54 4F 52
1346 21AF 59 2D 2D 53
1347 21B3 45 41 52 43
1348 21B7 48 20 53 50
1349 21BB 45 43 2C 4C
1350 21BF 49 53 54 20
1351 21C3 46 49 4C 45
1352 21C7 3F 9B

DLMO PAGE
BYTE 'DIRECTORY--SEARCH SPEC, LIST FILE?', CR

```

1353
1354
1355
1356
1357 21C9 0D 23
1358 21CB 20 CF 30
1359 21CE 20 C4 30
1360
1361 21D1 20 6E 26
1362
1363
1364
1365 21D4 AD 7C 1D
1366 21D7 C9 44
1367 21D9 F0 1A
1368 21DB A9 E5
1369 21DD A2 21
1370 21DF 20 B5 31
1371 21E2 4C B6 20
1372 21E5 4E 4F 54 20
1373 21E9 41 20 44 49
1374 21ED 53 4B 20 46
1375 21F1 49 4C 45 9B
1376 21F5
1377 0021
1378 00E5
1379 21F5 A2 10
1380 21F7 AD 9E 15
1381 21FA C9 4E
1382 21FC D0 0B
1383 21FE A9 21
1384 2200 9D 42 03
1385 2203 20 EE 31
1386 2206 4C B6 20
1387 2209 A9 F7
1388 220B A2 22
1389 220D 20 B5 31
1390 2210 A9 00
1391 2212 8D 02 1F
1392 2215 A2 20
1393 2217 A9 21
1394 2219 9D 42 03
1395 221C A9 F1
1396 221E 9D 44 03
1397 2221 A9 1D
1398 2223 9D 45 03
1399 2226 A9 44
1400 2228 8D F1 1D
1401 222B A9 3A
1402 222D 8D F3 1D
1403 2230 AD 7D 1D
1404 2233 C9 3A
1405 2235 D0 02
1406 2237 A9 31

      ***** DELETE FILE ROUTINE *****
      DELFIL WORD DEMG
      JSR GETIC1
      JSR PERX          ;EXIT IF PARAM ERRORS
      JSR CHKVER        ;BE SURE THAT IT IS VER. 2 DISKETTE
      CONTINUE WITH DELETE - ALLOW ONLY FOR DISK DEVICE ID
      LDA PAR           ;GET DEVICE
      CMP #'D           ;ONLY ALLOW DELETE FOR D:
      BEQ DF1
      LDA #.LOW.NDFL
      LDX #.LOW.NDFH
      JSR DSPLIN
      JMP MENUSL
      NDF .BYTE 'NOT A DISK FILE',CR
      HILO NDF
      +NDFH = NDF/256
      +NDFL = (-256)*NDFH+NDF
      DF1 LDX ##10
      LDA OPT
      CMP #'N           ;IF OPTION=N, NO QUERY
      BNE DWQ           ;NO, DELETE WITH QUERY
      LDA #DELETE
      STA ICCOM,X
      JSR CIOCL
      JMP MENUSL
      DWQ LDA #.LOW.TYGL
      LDX #.LOW.TYQH
      JSR DSPLIN        ;SAY TYPE Y TO DELETE...
      LDA #0
      STA IPTR          ;HOW MANY FILES TO SKIP, NONE AT FIRST
      LDX ##20          ;SET UP DELETE IOCB
      LDA #DELETE
      STA ICCOM,X
      LDA #.LOW.DB3L
      STA ICBAL,X
      LDA #.LOW.DB3H
      STA ICBAL,X
      LDA #'D
      STA DBUF-3
      LDA #''
      STA DBUF-1
      LDA PAR+1         ;DEVICE NUMBER OR : FROM OP INPUT
      CMP #''
      BNE **+4
      LDA #'1

```



```

1407 2239 8D F2 1D
1408 223C A2 10
1409 223E A9 03
1410 2240 9D 42 03
1411 2243 A9 06
1412 2245 9D 4A 03
1413 2248 A9 7C
1414 224A 9D 44 03
1415 224D A9 1D
1416 224F 9D 45 03
1417 2252 20 EE 31
1418 2255 A9 F4
1419 2257 9D 44 03
1420 225A A9 1D
1421 225C 9D 45 03
1422 225F A9 05
1423 2261 9D 42 03
1424 2264 A9 00
1425 2266 8D 01 1F
1426
1427
1428
1429 2269 A2 10
1430 226B A9 00
1431 226D 9D 48 03
1432 2270 A9 01
1433 2272 9D 49 03
1434 2275 20 EE 31
1435 2278 AD F5 1D
1436 227B C9 20
1437 227D D0 68
1438 227F EE 01 1F
1439 2282 AD 01 1F
1440 2285 CD 02 1F
1441 2288 30 DF
1442 228A A2 00
1443 228C A0 02
1444
1445
1446
1447 228E B9 F4 1D
1448 2291 C9 20
1449 2293 F0 09
1450 2295 9D F4 1D
1451 2298 E8
1452 2299 C8
1453 229A E0 08
1454 229C 30 F0
1455
1456
1457
1458 229E A9 2E
1459 22A0 9D F4 1D
1460 22A3 E8

IDRD STA DBUF-2 ; KLUDGE KLUDGE KLUDGE
LDX ##10
LDA #OPEN
STA ICCOM, X
LDA #6
STA ICAX1, X ; DIR READ OPEN
LDA #PARL
LDA ICBAL, X
LDA #PARH
STA ICBAH, X
JSR CIOCL
LDA #.LOW.DBUFL
STA ICBAL, X
LDA #.LOW.DBUFH
STA ICBAH, X
LDA #GETREC
STA ICCOM, X
LDA #0
STA PTR ; HOW MANY FILES WE HAVE SKIPPED

; READ FILENAME FROM DIR, QUERY AND DELETE
RDFN LDX ##10
LDA #0
STA ICBLL, X
LDA #1
STA ICBLH, X
JSR CIOCL ; READ A LINE FROM DIRECTORY
LDA DBUF+1 ; IF FILE LINE, THIS IS BLANK
CMP #'
BNE DELX ; THIS IS FREE BLOCKS LINE
INC PTR ; COUNT THIS FILE
LDA PTR ; HAVE WE SKIPPED ENUF YET
CMP IPTR
BMI RDFN ; BR IF NO
LDX #0 ; PUT PTR
LDY #2 ; GET PTR

; MESSAGE DELETE FILE NAMES
MDN1 LDA DBUF, Y
CMP #' ; END OF FILENAME
BEQ MDN2
STA DBUF, X
INX
INY
CPX #8
BMI MDN1

; FILENAME IS MOVED, PUT .EXT
MDN2 LDA #'
STA DBUF, X
INX

```

PAGE 38

ADDRESS	DATA	OPERATION	COMMENT
1461	22A4	A0 OA	
1462	22A6	B9 F4 1D	MDN3
1463	22A9	9D F4 1D	
1464	22AC	C8	
1465	22AD	E8	
1466	22AE	C0 OD	
1467	22B0	30 F4	
1468	22B2	8E 00 1F	
1469	22B5	A9 3F	
1470	22B7	9D F4 1D	
1471	22BA	E8	
1472	22BB	A9 9B	
1473	22BD	9D F4 1D	
1474	22C0	A9 F1	
1475	22C2	A2 1D	
1476	22C4	20 B5 31	
1477	22C7	20 7E 30	
1478	22CA	C9 59	
1479	22CC	D0 9B	
1480	22CE	AD 01 1F	
1481	22D1	8D 02 1F	
1482	22D4	AE 00 1F	
1483	22D7	A9 9B	
1484	22D9	9D F4 1D	
1485	22DC	A2 20	
1486	22DE	20 EE 31	
1487	22E1	20 ED 22	
1488	22E4	4C 3C 22	
1489	22E7	20 ED 22	
1490	22EA	4C B6 20	
1491	22ED	A2 10	
1492	22EF	A9 0C	
1493	22F1	9D 42 03	
1494	22F4	4C EE 31	
1495	22F7	54 59 50 45	
1496	22FB	20 22 59 22	
1497	22FF	20 54 4F 20	
1498	2303	44 45 4C 45	
1499	2307	54 45 2E 2E	
1500	230B	2E 9B	
1501	230D		
1502	0022		
1503	00F7		
1504	230D	44 45 4C 45	
1505	2311	54 45 20 46	
1506	2315	49 4C 45 20	
1507	2319	53 50 45 43	
1508	231D	9B	
1509			

```

1510 . PAGE
1511 ; **** COPY FILE ROUTINE ****
1512 ;
1513 ;
1514 231E 43 4F 50 59 CPMG . BYTE 'COPY--FROM, TO?', CR
1515 2322 2D 2D 46 52
1516 2326 4F 4D 2C 20
1517 232A 54 4F 3F 9B
1518 232E 4F 50 54 49 OE . BYTE 'OPTION NOT ALLOWED', CR
1519 2332 4F 4E 20 4E
1520 2336 4F 54 20 41
1521 233A 4C 4C 4F 57
1522 233E 45 44 9B
1523 2341
1524 0023 +OEHILO OE
1525 002E +OEL = OE/256
1526 ; (-256)*OE+OE
1527 ;
1528 ;
1529 ;
1530 ;
1531 2341 WCFLAG: . RES 1
1532 2342 WCSKP1: . RES 1
1533 2343 WCSKP2: . RES 1
1534 0014 WCBUFL = 20
1535 2344 WCBUF: . RES WCBUFL
1536 2358 20 20 43 4F WCOPYM . BYTE ' COPYING---'
1537 235C 50 59 49 4E
1538 2360 47 2D 2D 2D
1539 2364 44 4E 3A WCBUF2 . BYTE 'DN:'
1540 2367 . RES WCBUFL-3
1541 2378 1E 23 CPYFIL . WORD CPMG ; COPY FILE PROMPT
1542 237A 20 CF 30 JSR GETIC1 ; GET SOURCE DEVICE, ETC.
1543 237D AD 01 1F LDA PTR
1544 2380 BD 00 1F STA SAVX
1545 2383 AD 7C 1D LDA PAR ; GET 1ST CHAR. OF DEVICE
1546 2386 C9 44 CMP #'D ; TEST IF IT IS THE DISK
1547 2388 D0 07 BNE JMPNWC ; BR IF NOT THE DISK (THEN USE OLD CODE)
1548 238A A2 00 LDX #0 ; LOOK AT SOURCE FILE SPEC.
1549 238C 20 D7 2E JSR LOOKWC ; LOOK FOR WILDCARDS IN FILE SPEC.
1550 238F F0 03 BEG CPYFL1 ; BRANCH IF WILDCARDS USED IN DISK SPEC.
1551 2391 4C E1 24 JMP NOTWC ; USE OLD CODE
1552 2394 A9 80 CPYFL1 LDA ##80
1553 ;
1554 ;
1555 2396 8D 41 23 WCINIT STA WCFILAG ; 'WILDCARD' MODE (COPY-FILE OR DUP-FIL
1556 2399 A9 00 LDA #0
1557 239B 8D 42 23 STA WCSKP1
1558 ;
1559 239E A9 00 WCOPYL LDA #0
1560 23A0 8D 43 23 STA WCSKP2
1561 23A3 A2 10 LDX ##10 ; OPEN DIRECTORY
1562 23A5 A9 06 LDA #6
1563 23A7 9D 4A 03 STA ICAX1, X

```

```

1564 23AA A9 03          LDA    #OPEN
1565 23AC 9D 42 03        STA    ICCOM, X
1566 23AF A9 7C          LDA    #. LOW. PAR
1567 23B1 9D 44 03        STA    ICBAL, X
1568 23B4 A9 1D          LDA    #. HIGH. PAR
1569 23B6 9D 45 03        STA    ICBAL, X
1570 23B9 20 EE 31        JSR    CIOCL
1571
1572
1573 23BC A9 05          WCOPYR LDA    #GETREC      ; READ DIRECTORY
1574 23BE 9D 42 03        STA    ICCOM, X
1575 23C1 A9 14          LDA    #WCBUFL
1576 23C3 9D 48 03        STA    ICBLL, X
1577 23C6 A9 00          LDA    #0
1578 23C8 9D 49 03        STA    ICBLLH, X
1579 23CB A9 44          LDA    #. LOW. WCBUF
1580 23CD 9D 44 03        STA    ICBAL, X
1581 23D0 A9 23          LDA    #. HIGH. WCBUF
1582 23D2 9D 45 03        STA    ICBAL, X
1583 23D5 20 EE 31        JSR    CIOCL
1584
1585 23D8 AD 44 23        LDA    WCBUF      ; IF 1ST CHAR. OF DIR READ IS A #-IT IS T
1586 23DB C9 30          CMP    #'0
1587 23DD 90 0F          BCC    WCGOT
1588 23DF C9 3A          CMP    #'1
1589 23E1 80 0B          BCS    WCGOT
1590
1591 23E3 A9 0C          LDA    #CLOSE      ; ALL DONE -- NORM EXIT OF WILDCARD COPY
1592 23E5 9D 42 03        STA    ICCOM, X
1593 23E8 20 EE 31        JSR    CIOCL
1594 23EB 4C B6 20        JMP    MENUSL
1595
1596
1597 23EE AD 42 23        WCGOT  LDA    WCSKP1      ; IF ALREADY COPIED OR SKIPPED THIS FILE
1598 23F1 CD 43 23        CMP    WCSKP2
1599 23F4 F0 05          BEQ    SKIP1
1600
1601 23F6 EE 43 23        INC    WCSKP2
1602 23F9 D0 C1          BNE    WCOPYR
1603
1604 23FB EE 42 23        SKIP1  INC    WCSKP1
1605
1606 23FE A9 0C          LDA    #CLOSE      ; CLOSE DIRECTORY READ FILE
1607 2400 9D 42 03        STA    ICCOM, X
1608 2403 20 EE 31        JSR    CIOCL
1609
1610
1611 2406 A0 02          SYSLOP LDY    #2          ; DON'T COPY .SYS FILES
1612 2408 B9 4E 23        LDA    WCBUF+10, Y
1613 240B D9 15 24        CMP    DOTSYS, Y
1614 240E D0 0B          BNE    NOSYS
1615 2410 88            DEY
1616 2411 10 F5          BPL    SYSLOP
1617 2413 30 89          BMI    WCOPYL

```

```

1618
1619 2415 53 59 53      ;
1620                      DOTSYS . BYTE 'SYS'
1621 2418 A0 31          NOSYS LDY #1 ; CALC SOURCE DRIVE NUMBER
1622 241A AD 7D 1D      LDA PAR+1
1623 241D C9 3A          CMP #'
1624 241F F0 01          BEQ WCGOT1
1625 2421 AB            TAY
1626 2422 BC 65 23      WCGOT1 STY WCBUF2+1
1627
1628                      ;
1629 2425 A2 02          LDX #2 ; COMPRESS SPACES, ADD ':', ADD 'CR'
1630 2427 A0 03          LDY #3
1631
1632 2429 BD 44 23      ;
1633 242C C9 20          COMPR1 LDA WCBUF, X
1634 242E F0 04          CMP #'
1635 2430 99 64 23      BEQ COMPR2
1636 2433 CB            STA WCBUF2, Y
1637                      INY
1638 2434 EB            ;
1639 2435 E0 0A          COMPR2 INX
1640 2437 D0 F0          CPX #10
1641                      BNE COMPR1
1642 2439 BD 44 23      ;
1643 243C C9 20          LDA WCBUF, X
1644 243E F0 16          CMP #'
1645 2440 A9 2E          BEQ COMPR5
1646 2442 99 64 23      LDA #'
1647 2445 CB            STA WCBUF2, Y
1648 2446 BD 44 23      INY
1649 2449 C9 20          COMPR3 LDA WCBUF, X
1650 244B F0 04          CMP #'
1651 244D 99 64 23      BEQ COMPR4
1652 2450 CB            STA WCBUF2, Y
1653 2451 EB            INY
1654 2452 E0 0D          COMPR4 INX
1655 2454 D0 F0          CPX #13
1656                      BNE COMPR3
1657 2456 A9 9B          ;
1658 2458 99 64 23      COMPR5 LDA #CR
1659                      STA WCBUF2, Y
1660
1661 245B A9 5B          ;
1662 245D A2 23          LDA #. LOW. WCOPYM ; PRINT 'COPYING---DEV:FILENAME.EXT' MSG
1663 245F 20 B5 31      LDX #. HIGH. WCOPYM
1664                      JSR DSPLIN
1665 2462 2C 41 23      ;
1666 2465 50 0F          BIT WCFLAG
1667                      BVC WCOPY ; BR TO MIDDLE OF DUP FILE ROUTINE IF DU
1668 2467 A2 10          LDX ##10 ; SET UP BUFR ADDR TO PNT TO WLD CARD FIL
1669 2469 A9 64          LDA #. LOW. WCBUF2
1670 246B 9D 44 03      STA ICBAL, X
1671 246E A9 23          LDA #. HIGH. WCBUF2

```

```

1672 2470 9D 45 03          STA      ICBAL, X
1673 2473 4C 4F 2D          JMP      WCDUPS
1674
1675 2476 20 41 2E          WCOPY   JSR      USEPGM      ; SET BUFFER SIZES
1676 2479 A2 10              LDX      #$10          ; OPEN COPY SOURCE FILE
1677 247B A9 03              LDA      #OPEN
1678 247D 9D 42 03          STA      ICCOM, X
1679 2480 A9 04              LDA      #4
1680 2482 9D 4A 03          STA      ICAX1, X
1681 2485 A9 64              LDA      #.LOW.WCBUF2
1682 2487 9D 44 03          STA      ICBAL, X
1683 248A A9 23              LDA      #.HIGH.WCBUF2
1684 248C 9D 45 03          STA      ICBAL, X
1685 248F 8E FE 1E          STX      CSRC
1686 2492 20 EE 31          JSR      CIOCL
1687
1688 2495 A2 20              LDX      #$20
1689 2497 20 DD 31          JSR      PIOCBB      ; GET COPY DESTINATION FILE
1690 249A AD 01 1F          LDA      PTR          ; SAVE PTR, IPTR- MIGHT REPET GETTING 2ND
1691 249D
1692 249D 4B              MES      PHA
1693 249E AD 02 1F          LDA      IPTR
1694 24A1 4B              PHA
1695 24A2 20 EB 30          JSR      GETFIL      ; GET 2ND FILE NAME TO PAR
1696 24A5 6B              PLA          ; RECOVER IPTR, PTR
1697 24A6 8D 02 1F          STA      IPTR
1698 24A9 6B              PLA
1699 24AA 8D 01 1F          STA      PTR
1700 24AD AE 00 1F          LDX      SAVX
1701 24B0 8D 7C 1D          LDA      PAR, X
1702 24B3 C9 44              CMP      #'D
1703 24B5 F0 03              BEQ      WCOPY0
1704 24B7 4C 5E 25          JMP      PDES          ; JUMP TO OLD CPY-FILE CODE IF NOT DSK DES
1705
1706 24BA A0 31              WCOPY0 LDY      #'1          ; CALCULATE DESTINATION DRIVE #
1707 24BC 8D 7D 1D          LDA      PAR+1, X
1708 24BF C9 3A              CMP      #'1
1709 24C1 F0 01              BEQ      WCOPY1
1710
1711 24C3 AB              TAY
1712 24C4 CC 65 23          WCOPY1 CPY      WCBUF2+1
1713 24C7 D0 06              BNE      WCOPY2
1714 24C9 20 AA 19          JSR      CLOSX          ; CANT COPY TO SAME DRIVE NMNR - ERR & EXI
1715
1716 24CC 4C 74 25          JMP      ODMS
1717
1718
1719 24CF A2 20              WCOPY2 LDX      #$20
1720 24D1 8C 65 23          STY      WCBUF2+1      ; CHANGE FILESPEC TO DESTINATION
1721 24D4 A9 64              LDA      #.LOW.WCBUF2
1722 24D6 9D 44 03          STA      ICBAL, X
1723 24D9 A9 23              LDA      #.HIGH.WCBUF2
1724 24DB 9D 45 03          STA      ICBAL, X
1725 24DE 4C 94 25          JMP      OPDES1      ; CONTINUE INTO OLD COPY-FILE CODE

```

```

1726
1727
1728 24E1      NOTWC      =      *
1729 24E1      A2 20      LDX      ##20      ; IOCB 3
1730 24E3      20 DD 31    JSR      PIOCIB
1731 24E6      20 E8 30    JSR      GETFIL      ; GET SECOND FILENAME
1732
1733      ; MAKE SURE DESTINATION IS NOT DOS.SYS
1734
1735 24E9      AE 00 1F      LDX      SAVX      ; ENTRY-INDEX TO DEST FILE SPEC
1736 24EC      20 ED 2E      JSR      TSTDOS      ; WON'T RETURN IF IS DOS.SYS
1737
1738 24EF      AE 00 1F      LDX      SAVX
1739 24F2      20 D7 2E      JSR      LOOKWC
1740 24F5      D0 30      BNE      NWCIND      ; BRANCH IF NO WILDCARDS IN DESTINATION
1741 24F7      A9 01      LDA      #.LOW.NWAL
1742 24F9      A2 25      LDX      #.LOW.NWAH
1743 24FB      20 B5 31      JSR      DSPLIN
1744 24FE      4C B6 20      JMP      MENUSL
1745 2501      57 49 4C 44    NWA      .BYTE      'WILD CARDS NOT ALLOWED IN DESTINATION',CR
1746 2505      20 43 41 52
1747 2509      44 53 20 4E
1748 250D      4F 54 20 41
1749 2511      4C 4C 4F 57
1750 2515      45 44 20 49
1751 2519      4E 20 44 45
1752 251D      53 54 49 4E
1753 2521      41 54 49 4F
1754 2525      4E 9B
1755 2527
1756 0025      +NWAH      =      NWA
1757 0001      +NWAL      =      NWA/256
1758 2527      NWCIND      =      *
1759 2527      20 C4 30      JSR      PERX      ; IF PARAM ERRS. EXIT
1760 252A      20 41 2E      JSR      USEPGM      ; ASK USR IF CAN USE PGM AREA OR DATA BFR
1761 252D      PSRC      =      *
1762 252D      AD 7C 1D      LDA      PAR      ; GET 1ST LETR OF PARAM
1763 2530      C9 4B      CMP      #'K
1764 2532      F0 40      BEQ      ODMS      ; K: GETS 'OPTION DOESNT MAKE SENSE' FOR N
1765 2534      C9 43      CMP      #'C
1766 2536      F0 3C      BEQ      ODMS      ; C: GETS 'OPTION DOESNOT MAKE SENSE' FOR
1767 2538      C9 45      CMP      #'E      ; E: AS SOURCE IS SPECIAL
1768 253A      D0 0B      BNE      OPSRC      ; IF NO THEN OPEN SOURCE FILE
1769 253C      A2 00      LDX      #0
1770 253E      8E FE 1E      STX      CSRC
1771 2541      4C 5E 25      JMP      PDES
1772 2544      C9 53      OPSRC      CMP      #'S
1773 2546      F0 2C      BEQ      ODMS      ; S: AS SOURCE GETS O. D. M. S. FOR NOW
1774
1775      ; OPEN SOURCE FILE
1776
1777 2548      A2 10      LDX      ##10
1778 254A      A9 03      LDA      #OPEN
1779 254C      9D 42 03      STA      ICCOM, X

```

```

1780 254F A9 04          LDA      #4          ; OPEN IN
1781 2551 9D 4A 03      STA      ICAX1,X
1782 2554 8E FE 1E      STX       CSRC
1783 2557 E0 10          CPX       #$10
1784 2559 D0 1F          BNE      *+33
1785 255B 20 EE 31      JSR       CIOCL          ; OPEN SOURCE FILE HERE
1786
1787                      ;
1788                      ; READY FOR OPEN OF DESTINATION
1789 255E AE 00 1F      PDES      LDX      SAVX
1790 2561 BD 7C 1D      LDA      PAR,X
1791
1792 2564 C9 4B          CMP      #'K          ; IS DEST KEYBOARD?
1793 2566 F0 0C          BEQ      ODMS          ; YES, THEN CAN'T DO IT
1794
1795 2568 C9 45          CMP      #'E          ; CHECK FOR SPECIAL CASE
1796 256A D0 15          BNE      OPDES          ; IF NOT
1797 256C A9 00      PDES1      LDA      #0          ; SPECIAL CASE - DONT OPEN, USE EXISTING
1798 256E 8D FF 1E      STA      CDES
1799 2571 4C AB 25      JMP      DDCPY
1800 2574 A9 2E      ODMS      LDA      #DEL
1801 2576 A2 23      LDX      #DEH          ; SAY OPTION NOT ALLOWED
1802 2578 20 B5 31      JSR      DSPLIN
1803 257B 20 AA 19      JSR      CLOSX          ; CLOSE IOCB 1 & 2
1804 257E 4C B6 20      JMP      MENUSL
1805
1806 2581 C9 43      OPDES      CMP      #'C
1807 2583 F0 EF      BEQ      ODMS          ; C: GETS 'OPTION DOESNOT MAKE SENSE' FOR
1808 2585 AE 9E 15      LDX      OPT          ; GET 2ND FILE OPTION
1809
1810 2588 E0 41          CPX      #'A          ; APPEND TO DISK FILE
1811 258A D0 08          BNE      OPDES1
1812 258C C9 44          CMP      #'D
1813 258E D0 E4          BNE      ODMS
1814 2590 A9 09      LDA      #9
1815 2592 D0 02          BNE      OPDES3
1816 2594 A9 08      OPDES1      LDA      #8
1817 2596 A2 20      OPDES3      LDX      #$20
1818 2598 9D 4A 03      STA      ICAX1,X          ; OPEN TYPE OUT
1819 259B A9 03      LDA      #OPEN
1820 259D 9D 42 03      STA      ICCOM,X OPEN
1821 25A0 8E FF 1E      STX       CDES
1822 25A3 20 EE 31      JSR      CIOCL
1823 25A6 A9 00      LDA      #0
1824 25A8 9D 4B 03      STA      ICAX2,X
1825
1826                      ;
1827                      ; COPY FROM CSRC TO CDES
1828 25AB A9 07      DDCPY      LDA      #GETCHR
1829 25AD AE FE 1E      GC1      LDX      CSRC
1830 25B0 AC FF 1E      LDY      CDES
1831 25B3 9D 42 03      STA      ICCOM,X
1832 25B6 A9 0B      LDA      #PUTCHR
1833 25B8 99 42 03      STA      ICCOM,Y

```


ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 45

```

1834 25BB A5 1A          LDA      BUFADR      ; ADDRESS OF BUFFER - EITHER
1835 25BD 9D 44 03      STA      ICBAL, X      ; PGM AREA (MEMLO) OR DATA BUFFER (DBUF)
1836 25C0 99 44 03      STA      ICBAL, Y
1837 25C3 A5 1B          LDA      BUFADR+1    ; BUFADR IN LSB, MSB ORDER
1838 25C5 9D 45 03      STA      ICBAL, X
1839 25C8 99 45 03      STA      ICBAL, Y
1840 25CB AE FE 1E      CLOOP  LDX      CSRC
1841 25CE AD 04 1F      LDA      BUFLN      ; LENGTH OF BUFFER ADDRESSED
1842 25D1 9D 48 03      STA      ICBLL, X      ; BY BUFADR
1843 25D4 AD 05 1F      LDA      BUFLN+1    ; BOTH BUFADR & BUFLN ARE ASSIGNED
1844 25D7 9D 49 03      STA      ICBLL, X      ; IN SUBROUTINE USEPGM
1845 25DA 20 56 E4      JSR      CIO      ; READ FROM INPUT
1846 25DD 8C F8 1E      STY      SSTAT
1847 25E0 AE FF 1E      LDX      CDES
1848 25E3 AC FE 1E      LDY      CSRC
1849 25E6 B9 48 03      LDA      ICBLL, Y
1850 25E9 9D 48 03      STA      ICBLL, X
1851 25EC B9 49 03      LDA      ICBLL, Y
1852 25EF 9D 49 03      STA      ICBLL, X
1853 25F2 19 48 03      ORA      ICBLL, Y      ; IF SOURCE FILE LENGTH = 0
1854 25F5 F0 03          BEQ      CKRS      ; DON'T DO WRITE
1855 25F7 20 EE 31      JSR      CIOCL      ; WRITE, ABORT IF ERROR
1856 25FA AD F8 1E      CKRS  LDA      SSTAT      ; GET READ OPERATION STATUS BACK
1857 25FD 10 CC          BPL      CLOOP      ; IF OK, GO READ SOME MORE
1858 25FF C9 B8          CMP      #$88      ; EOF STATUS
1859 2601 F0 03          BEQ      **+5
1860 2603 4C F6 31      JMP      CIOER      ; IF NOT, ABORT
1861 2606 AE FE 1E      CLOC  LDX      CSRC
1862 2609 F0 0B          BEQ      DU4      ; IF E:, DONT CLOSE
1863
1864          ; CLOSE SOURCE FILE
1865
1866 260B A9 0C          LDA      #CLOSE
1867 260D 9D 42 03      STA      ICCOM, X
1868 2610 20 56 E4      JSR      CIO
1869 2613 AE FF 1E      DU4   LDX      CDES
1870 2616 F0 0B          BEQ      DU3      ; IF DES=E:
1871 2618 A9 0C          LDA      #CLOSE
1872 261A 9D 42 03      STA      ICCOM, X
1873 261D 20 56 E4      JSR      CIO
1874 2620 AE FF 1E      DU3   LDX      CDES
1875 2623 D0 07          BNE      DU6
1876 2625 A9 E9          LDA      #. LOW. DDSK+1
1877 2627 A2 26          LDX      #. HIGH. (DDSK+1)
1878 2629 20 BE 19      JSR      PRNMSG      ; PRNT A CR BEFOR SELECT OR WLD CARD PRMPT
1879 262C          DU6   =      *
1880
1881 262C 2C 41 23      BIT      WCFLAG
1882 262F 10 03          BPL      DU5
1883 2631 4C 9E 23      JMP      WCOPYL      ; BRANCH BACK TO WILD CARD LOOP
1884 2634 4C B6 20      DU5   JMP      MENU5L

```

```

1885
1886
1887
1888
1889
1890
1891
1892
1893
1894 2637 52 26
1895 2639 20 CF 30
1896 263C 20 DA 30
1897 263F 20 C4 30
1898
1899 2642 20 6E 26
1900
1901
1902
1903 2645 A9 20
1904 2647 A2 10
1905 2649 9D 42 03
1906 264C 20 EE 31
1907 264F 4C B6 20
1908 2652 52 45 4E 41
1909 2656 4D 45 20 2D
1910 265A 20 47 49 56
1911 265E 45 20 4F 4C
1912 2662 44 20 4E 41
1913 2666 4D 45 2C 20
1914 266A 4E 45 57 9B
1915
1916
1917
1918
1919
1920 266E A0 01
1921 2670 AD 7D 1D
1922 2673 C9 3A
1923 2675 F0 03
1924 2677 29 0F
1925 2679 A8
1926 267A 8C F6 1E
1927
1928 267D 4C F3 28
1929

```

```

PAGE
**** RENAME FILE ROUTINE ****

; RENAME SETS UP IOCB #1 WITH THE OLD FILE NAME AND THE BUFFER ADDRESS
; POINTS TO THE NEW FILE NAME. THE NEW FILE SPECIFICATION CANNOT HAVE
; A DEVICE ID. THE DEVICE ID IS THE SAME AS SPECIFIED FOR THE OLD FILE
; D2: ABC.S2, QQQ.R3 THIS RENAMES ABC.S2 ON DRIVE #2 TO QQQ.R3
;
RENFIL WORD RNMG
      JSR GETIC1 ; GET OLD FILE SPEC & PUT ADDR IN IOCB
      JSR GETNAME ; GET NEW FILE NAME
      JSR PERX ; EXIT IF PARAMETER ERRORS
;
      JSR CHKVER ; MAKE SURE VER 2 DISKETTE
;
      CONTINUE WITH RENAME
;
      LDA #RENAME
      LDX ##10
      STA ICCOM, X
      JSR CIOCL
      JMP MENUSL
RNMG BYTE 'RENAME - GIVE OLD NAME, NEW', CR

; ***** SUBROUTINE *****
;
; MAKE SURE THIS IS A VERSION 2 FORMAT DISK
;
CHKVER LDY #1 ; ASSUME DRIVE 1- GET DRIVE #
      LDA PAR+1 ; TEST CHAR 2 OF FILE SPEC FOR SEMICOLON
      CMP #' ; IF IS, USING DEFAULT DRIVE (1)
      BEQ DRV1 ; IT IS, SO SAVE DRIVE #
      AND ##0F ; ELSE CHAR 2 IS ASCII REP OF DRIVE #
      TAY ; CONVERT TO BINARY & SAVE IT
      STY UNNO ; SAVE DRIVE #
;
      JMP TSTVER2 ; TST FOR VERS. 2 DISK- WONT RETURN IF NOT

```

```

1930
1931
1932
1933
1934 2680 B9 26
1935 2682 20 3C 30
1936 2685 20 BE 32
1937 2688 18
1938 2689 69 30
1939 268B BD EB 26
1940 268E BD EB 26
1941 2691 20 C4 30
1942 2694 A9 D0
1943 2696 A2 26
1944 2698 20 B5 31
1945 269B 20 7E 30
1946 269E C9 59
1947 26A0 D0 14
1948 26A2 A9 EA
1949 26A4 A2 10
1950 26A6 9D 44 03
1951 26A9 A9 26
1952 26AB 9D 45 03
1953 26AE A9 FE
1954 26B0 9D 42 03
1955 26B3 20 EE 31
1956 26B6 4C B6 20
1957 26B9 57 48 49 43
1958 26BD 48 20 44 52
1959 26C1 49 56 45 20
1960 26C5 54 4F 20 46
1961 26C9 4F 52 4D 41
1962 26CD 54 3F 9B
1963 26D0 54 59 50 45
1964 26D4 20 22 59 22
1965 26D8 20 54 4F 20
1966 26DC 46 4F 52 4D
1967 26E0 41 54 20 44
1968 26E4 49 53 4B 20
1969 26E8
1970 26E9 9B
1971 26EA 44
1972 26EB
1973 26EC 3A 9B
1974 26EE
1975 0026
1976 00B9
1977 26EE
1978 0026
1979 00D0
1980 26EE
1981 0026
1982 00EA

      .PAGE
      **** FORMAT DISK ROUTINE ****

FMTDSK .WORD WHD
      JSR GETLIN
      JSR GETDN
      CLC
      ADC #'0
      STA DDSK
      STA CDSK
      JSR PERX
      LDA #.LOW.VFML ;QUERY TO VERIFY DRIVE NUMBER
      LDX #.LOW.VFMH
      JSR DSPLIN
      JSR CHRGET
      CMP #'Y ;SEE IF OK
      BNE FMX
      LDA #.LOW.FDPL
      LDX ##10
      STA ICBAL,X
      LDA #.LOW.FDPH
      STA ICBAL,X
      LDA #FORMAT
      STA ICCOM,X
      JSR CIOCL ;CALL CIO TO DO FORMAT
      JMP MENUCL ;EXIT.
      WHD .BYTE 'WHICH DRIVE TO FORMAT?',CR

VFM .BYTE 'TYPE ',#22,'Y',#22,' TO FORMAT DISK '

DDSK: .RES 1
      .BYTE CR
FDP .BYTE 'D'
CDSK: .RES 1
      .BYTE ' ',CR
      HILO WHD
+WHDH = WHD/256
+WHDL = (-256)*WHDH+WHD
      HILO VFM
+VFMH = VFM/256
+VFML = (-256)*VFMH+VFM
      HILO FDP
+FDPH = FDP/256
+FDPL = (-256)*FDPH+FDP

```

```

1983                                     PAGE
1984                                     ; ***** START CARTRIDGE ROUTINE *****
1985                                     ;
1986                                     ;
1987  E45F      SYVBL      =      SYSVBV
1988  26EE      HILO      SYVBL
1989  00E4      +SYVBLH    =      SYVBL/256
1990  005F      +SYVBLL    =      (-256)*SYVBLH+SYVBL
1991  E462      XTVBL     =      XITVBV
1992  26EE      HILO      XTVBL
1993  00E4      +XTVBLH    =      XTVBL/256
1994  0062      +XTVBLL    =      (-256)*XTVBLH+XTVBL
1995  26EE      STCAR     WORD    SCMG      ; NO MSG, PRINT A <CR>
1996  BFFD      ROMTST    =      $BFFD
1997  26F0      LDY      ROMTST      ; TEST IF RAM OR OTHER
1998  26F3      LDA      #$AA      ; PATTERN #1
1999  26F5      STA      ROMTST
2000  26F8      CMP      ROMTST
2001  26FB      BNE      NOTRAM      ; BRANCH IF NOT RAM
2002  26FD      LDA      #$55      ; PATTERN #2
2003  26FF      STA      ROMTST
2004  2702      CMP      ROMTST
2005  2705      BNE      NOTRAM      ; BRANCH IF NOT RAM
2006                                     ;
2007  2707      STY      ROMTST      ; THERE IS VALID RAM - SAY NO CART
2008  270A      LDA      #.LOW.NCAL
2009  270C      LDX      #.LOW.NCAH      ; SAY NO CART
2010  270E      JSR      DSPLIN
2011  2711      JMP      MENUCL
2012                                     ;
2013                                     ; CHECK IF ROM OR EMPTY ADDRESS SPACE
2014                                     ;
2015  2714      AD FC BF      NOTRAM LDA      $BFFC      ; KNOWN ROM ZERO BYTE
2016  2717      DO F1      BNE      NOCART      ; BRANCH IF EMPTY ADDRESS SPACE
2017                                     ;
2018  2719      AA      TAX      ; SINCE EMPTY ADDR SPACE GIVES A RANDOM
2019  271A      AD FD BF      CKCART LDA      ROMTST      ; VALUE, TEST THE SAME LOC MANY TIMES.
2020  271D      FO EB      BEQ      NOCART      ; BRANCH IF NO CARTRIDGE
2021  271F      CD FD BF      CMP      ROMTST
2022  2722      DO E6      BNE      NOCART      ; BRANCH IF NO CARTRIDGE
2023  2724      E8      INX
2024  2725      DO F3      BNE      CKCART      ; LOOP BACK
2025                                     ;
2026                                     ;
2027                                     ; RESET VERTICAL BLANK VECTORS BEFORE ENTERING CART
2028                                     ;
2029  2727      20 76 19      JSR      INITIO
2030  272A      A9 06      LDA      #6      ; SET VVBLKI
2031  272C      A2 E4      LDX      #.LOW.SYVBLH      ; HI BYTE
2032  272E      A0 5F      LDY      #.LOW.SYVBLL
2033  2730      20 5C E4      JSR      SETVBV
2034  2733      A9 07      LDA      #7      ; SET VVBLKD
2035  2735      A2 E4      LDX      #.LOW.XTVBLH
2036  2737      A0 62      LDY      #.LOW.XTVBLL

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 49

2037 2739 20 5C E4
2038 273C 4C 12 19

JSR SETVBV
JMP CLMJMP

```

2039
2040 273F 4E 4F 20 43      NCA      .PAGE
2041 2743 41 52 54 52      .BYTE   'NO CARTRIDGE'
2042 2747 49 44 47 45
2043 274B 9B              SCMG      .BYTE   CR
2044 274C              HILO      NCA
2045 0027      +NCAH      =        NCA/256
2046 003F      +NCAL      =        (-256)*NCAH+NCA
2047
2048
2049      ***** RUN AT ADDRESS *****
2050
2051
2052
2053 274C 68 27      BRUN      .WORD   BRMG
2054 274E 20 3C 30      JSR      GETLIN
2055 2751 20 24 32      JSR      GETNO
2056 2754 20 C4 30      JSR      PERX
2057 2757 85 1A      STA      RAMLO
2058 2759 86 1B      STX      RAMLO+1
2059 275B AD 03 1F      LDA      CTR
2060 275E C9 04      CMP      #4
2061 2760 F0 50      BEQ      MOUT1      ;RETURN TO MENU IF NO RUN ADDRESS GIVEN
2062 2762 20 76 19      JSR      INITIO      ;CLOSE ALL IOCB'S, THEN REOPEN S/E
2063 2765 4C 20 19      JMP      LMTR        ;LOAD MEM. SAV & JUMP TO ADDRESS
2064
2065
2066 276B 52 55 4E 20      BRMG      .BYTE   'RUN FROM WHAT ADDRESS?', CR
2067 276C 46 52 4F 4D
2068 2770 20 57 48 41
2069 2774 54 20 41 44
2070 277B 44 52 45 53
2071 277C 53 3F 9B

```

2072
 2073
 2074
 2075
 2076 277F 54 59 50 45
 2077 2783 20 22 59 22
 2078 2787 20 54 4F 20
 2079 278B 43 52 45 41
 2080 278F 54 45 20 4D
 2081 2793 45 4D 2E 53
 2082 2797 41 56 9B
 2083 279A 7F 27
 2084 279C 20 7E 30
 2085 279F C9 59
 2086 27A1 D0 0C
 2087 27A3 20 73 18
 2088 27A6 30 0D
 2089 27AB A9 BD
 2090 27AA A2 27
 2091 27AC 20 B5 31
 2092 27AF 20 AA 19
 2093 27B2 4C B6 20
 2094
 2095
 2096
 2097 27B5 20 46 17
 2098 27B8 10 F5
 2099 27BA 4C F5 31
 2100
 2101 27BD 4D 45 4D 2E
 2102 27C1 53 41 56 20
 2103 27C5 46 49 4C 45
 2104 27C9 20 41 4C 52
 2105 27CD 45 41 44 59
 2106 27D1 20 45 58 49
 2107 27D5 53 54 53 9B
 2108 27D9
 2109 0027
 2110 00BD

**** CREATE MEM.SAV FILE ON DISK ****

MEMS .BYTE 'TYPE ', \$22, 'Y', \$22, ' TO CREATE MEM.SAV', CR

MEMSAV .WORD MEMS
 JSR CHRGET ; GET CHAR (CR)
 CMP #'Y
 BNE MOUT ; BRANCH IF USER'S ANSWER NOT A Y
 JSR MEMSVQ ; TRY TO OPEN MEM.SAV
 BMI MCONT ; IF FILE DOESN'T EXIST THEN JUMP
 LDA #.LOW.MEMSGH ; ELSE 'MEMORY.SAVE' ALREADY EXIST
 LDX #.LOW.MEMSGH
 JSR DSPLIN ; DISPLAY THIS FACT
 JSR CLOSX ; EXIT AFTER CLOSING IOCB1
 MOUT JMP MENUSL

WRITE MEMORY.SAVE TO DISK

MCONT JSR MWRITE ; WRITE FILE
 BPL MOUT
 MERR JMP CIDER1 ; DISPLAY ERROR

MEMSG .BYTE 'MEM.SAV FILE ALREADY EXISTS', CR

HILO MEMSG
 +MEMSGH = MEMSG/256
 +MEMSQL = (-256)*MEMSGH+MEMSG

```

2111          PAGE
2112          ***** WRITE DOS & DUP *****
2113
2114
2115 27D9 75 28      WBOOT      WORD      DOSDRV      ; ADDRESS OF DRIVE # PROMPT
2116
2117          ;
2118          RETRIEVE DRIVE NUMBER FROM USER.
2119
2119 27D8 20 3C 30      JSR      GETLIN      ; GET INPUT
2120 27DE 20 BE 32      JSR      GETDN      ; GET DRIVE AS NUMBER, VERIFY IT
2121 27E1 20 C4 30      JSR      PERX      ; EXIT IF ERROR
2122 27E4 8D F6 1E      STA      UNNO      ; SAVE IT FOR TSTVER2
2123 27E7 09 30      ORA      #'0      ; TURN BACK TO ASCII REP
2124 27E9 8D CB 28      STA      DS+1      ; STORE IN DOS.SYS FILE SPEC
2125 27EC 8D C7 28      STA      QWMG+31      ; & IN PROMPT
2126
2127 27EF 20 F3 28      JSR      TSTVER2      ; TST IF VERS. 2 DISK - IF ISNT WONT RTRN
2128
2129          ;
2130          ASK USER IF CAN WRITE DOS & DUP TO SPECIFIED DRIVE
2131
2131 27F2 A9 A8      LDA      #.LOW.QWMGL      ; PRINT PROMPT
2132 27F4 A2 28      LDX      #.LOW.QWMGH
2133 27F6 20 B5 31      JSR      DSPLIN
2134 27F9 20 7E 30      JSR      CHRGET
2135 27FC C9 59      CMP      #'Y
2136 27FE D0 72      BNE      WBX      ; EXIT UNLESS Y
2137
2138          ;
2139          TELL USER WRITING DOS FILES AND WRITE DOS.SYS FIRST- JUST OPEN IT.
2140
2140 2800 A9 92      LDA      #.LOW.WBMGL
2141 2802 A2 28      LDX      #.LOW.WBMGH
2142 2804 20 B5 31      JSR      DSPLIN
2143
2144 2807 A9 03      LDA      #OPEN
2145 2809 A2 10      LDX      ##10      ; OPEN DOS.SYS ON IOCB #1
2146 280B 9D 42 03      STA      ICCOM,X      ; WILL CAUSE FMS TO REWRITE BOOT SECTOR
2147 280E A9 CA      LDA      #.LOW.DSL      ; & A COPY OF DOS.SYS
2148 2810 9D 44 03      STA      ICBAL,X
2149 2813 A9 28      LDA      #.LOW.DSH
2150 2815 9D 45 03      STA      ICBAL,X
2151 2818 A9 08      LDA      #8
2152 281A 9D 4A 03      STA      ICAX1,X
2153 281D 20 EE 31      JSR      CIOCL      ; DO OPEN, IF ERROR GOTO MENU
2154
2155 2820 A2 10      LDX      ##10
2156 2822 A9 0C      LDA      #CLOSE
2157 2824 9D 42 03      STA      ICCOM,X
2158 2827 20 EE 31      JSR      CIOCL      ; DONE CLOSE IT.
2159
2160          ;
2161          WRITE DUP.SYS - SWAP AREA FILE
2162
2162 282A A2 0B      LDX      #11      ; MOVE 11 CHARS
2163 282C 8D 2E 18      MDUPBL LDA      DUPSYS-1,X
2164 282F 9D 7B 1D      STA      PAR-1,X      ; MOVE FILE NAME TO PARAMETER LIST

```


2165	2832	CA		DEX		
2166	2833	DO F7		BNE	MDUPBL	
2167	2835	AD CB 28		LDA	DS+1	; GET DRIVE NUMBER
2168	2838	8D 7D 1D		STA	PAR+1	; PUT IT IN DUP.SYS FILE SPEC
2169						
2170	283B	8E 01 1F		STX	PTR	
2171	283E	A2 10		LDX	##10	
2172	2840	20 DD 31		JSR	PIOCB	; PUT FILE NAME POINTER IN IOCB
2173	2843	A9 0C		LDA	#. LOW. DTHL	
2174	2845	8D E0 19		STA	LDST	
2175	2848	A9 1F		LDA	#. LOW. DTHH	
2176	284A	8D E1 19		STA	LDST+1	
2177	284D	A9 05		LDA	#. LOW. NMDUP	
2178	284F	8D E2 19		STA	LDND	
2179	2852	A9 F9		LDA	#. LOW. LENL	
2180	2854	8D F8 2F		STA	WDRL+1	
2181	2857	A9 13		LDA	#. LOW. LENH	
2182	2859	8D FD 2F		STA	WDRH+1	
2183	285C	A9 33		LDA	#. HIGH. NMDUP	
2184	285E	8D E3 19		STA	LDND+1	
2185	2861	48		PHA		; NO /A
2186	2862	A9 75		LDA	#. LOW. DOSOS	
2187	2864	8D E0 02		STA	RUNAD	
2188	2867	A9 20		LDA	#. HIGH. DOSOS	
2189	2869	8D E1 02		STA	RUNAD+1	; SET DUP.SYS RUN ADDRESS
2190	286C	CE BE 18		DEC	RUNG+1	; SET RUN FLAG
2191	286F	4C A0 2F		JMP	NRUNAD	; WRITE DUP.SYS
2192	2872	4C B6 20		JMP	MENUSL	
2193	2875	44 52 49 56	WBX	JMP		
2194	2879	45 20 54 4F	DOSDRV	BYTE		'DRIVE TO WRITE DOS FILES TO?', CR
2195	287D	20 57 52 49				
2196	2881	54 45 20 44				
2197	2885	4F 53 20 46				
2198	2889	49 4C 45 53				
2199	288D	20 54 4F 3F				
2200	2891	9B				
2201	2892	57 52 49 54	WBMG	BYTE		'WRITING NEW DOS FILES', CR
2202	2896	49 4E 47 20				
2203	289A	4E 45 57 20				
2204	289E	44 4F 53 20				
2205	28A2	46 49 4C 45				
2206	28A6	53 9B				
2207	28AB					
2208	0028		+WBMGH	=	WBMG/256	
2209	0092		+WBMGL	=	(-256)*WBMGH+WBMG	

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 54

2210
2211 28A8 54 59 50 45
2212 28AC 20 22 59 22
2213 28B0 20 54 4F 20
2214 28B4 57 52 49 54
2215 28B8 45 20 44 4F
2216 28BC 53 20 54 4F
2217 28C0 20 44 52 49
2218 28C4 56 45 20 20
2219 28C8 2E 9B
2220 28CA
2221 0028
2222 00A8
2223 28CA 44 31 3A 44
2224 28CE 4F 53 2E 53
2225 28D2 59 53 9B
2226 28D5
2227 0028
2228 00CA
2229 28D5 45 52 52 4F
2230 28D9 52 20 2D 20
2231 28DD 4E 4F 54 20
2232 28E1 56 45 52 53
2233 28E5 49 4F 4E 20
2234 28E9 32 20 46 4F
2235 28ED 52 4D 41 54
2236 28F1 2E 9B
2237 28F3
2238 0028
2239 00D5

PAGE
BYTE 'TYPE ', \$22, 'Y', \$22, ' TO WRITE DOS TO DRIVE ', CR

HILO QWMG
+QWMGH = QWMG/256
+QWMGL = (-256)*QWMGH+QWMG
DS . BYTE 'D1: DOS. SYS', CR

HILO DS
+DSH = DS/256
+DSL = (-256)*DSH+DS
WVD . BYTE 'ERROR - NOT VERSION 2 FORMAT.', CR

HILO WVD
+WVDH = WVD/256
+WVDL = (-256)*WVDH+WVD

```

2240      PAGE
2241      ; **** TEST FOR VERSION 2 FORMAT - SUBROUTINE ****
2242      ;
2243      ;
2244      ;
2245      ; SUBROUTINE - TSTVER2
2246      ;
2247      ; READS THE DISK'S VTOC AND CHECKS IF VERSION BYTE IS SET AS 2.
2248      ;
2249      ; ENTRY - DRIVE # STORED IN UNNO
2250      ; EXIT - RETURNS ONLY IF IS A VERSION 2 DISK
2251      ; ELSE DOES AN ERROR EXIT BACK TO MENU
2252      ; CALLS - DRVSTAT AND RVTOC
2253      ; CALLED BY - DELFIL, RENFIL, WBOOT.
2254      ;
2255      ;
2256      ; GET DRIVE TYPE SO KNOW CORRECT SECTOR SIZE - NEEDED FOR RVTOC
2257      ;
2258      TSTVER2 =      *
2259      28F3 A9 00      LDA      #0          ; GET DRIVE TYPE IN SECSIZ
2260      28F5 8D 08 1F    STA      SECSIZ      ; ASSUME 256 - NEEDED BY RVTOC
2261      28F8 AD F6 1E    LDA      UNNO        ; GET DRIVE #
2262      28FB 20 E4 2C    JSR      DRVSTAT     ; FIND OUT TYPE - CARRY FLAG
2263      28FE B0 05      BCS      OKTYP       ; BRANCH IF 256 TYPE
2264      2900 A9 80      LDA      #$80       ; ELSE SET AS 128 BYTE DEVICE
2265      2902 8D 08 1F    STA      SECSIZ
2266      ;
2267      ; READ THE VTOC & CHECK IF VERSION 2
2268      ;
2269      2905 20 26 2A    OKTYP JSR      RVTOC      ; READ IN VTOC TO DBUF
2270      2908 AD F4 1D    LDA      DBUF        ; 1ST BYTE IS VERSION #
2271      290B C9 02      CMP      #2          ; IS IT VERSION 2?
2272      290D F0 0A      BEQ      SMVRS       ; YES, SAME VERSION - RETURN
2273      ;
2274      ; NOT A VERSION 2 DISK - PRINT MSG & GOTO MENU
2275      ;
2276      290F A9 D5      LDA      #.LOW.WVDL   ; ELSE, NOT SAME VERSION
2277      2911 A2 28      LDX      #.LOW.WVDH   ; PRINT INCOMPATIBLE MSG
2278      2913 20 B5 31    JSR      DSPLIN
2279      2916 4C B6 20    JMP      MENU$L      ; GOTO MENU
2280      ;
2281      ; DISK IS VERSION TWO SO RETURN
2282      ;
2283      2919 60      SMVRS RTS          ; RETURN

```

```

2284
2285
2286
2287
2288 291A 5B 29 LDFIL WORD LFMG
2289 291C 20 CF 30 JSR GETIC1
2290 291F A9 00 LDA #0
2291 2921 AE 9E 15 LDX OPT
2292 2924 8D 9E 15 STA OPT
2293 2927 E0 4E CPX #N / IS OPTION N FOR DON'T LOAD AND GO?
2294 2929 D0 03 BNE NOTN / BRANCH IF NOT
2295 292B CE 9E 15 DEC OPT
2296 292E 20 C4 30 NOTN JSR PERX
2297 2931 20 A9 15 JSR LOAD
2298 2934 E0 00 CPX #0 / PROCESS LOAD SUBR RESPONSE
2299 2936 F0 12 BEQ LDFX / BRANCH IF LOAD WAS OK
2300 2938 E0 03 CPX #3
2301 293A F0 04 BEQ NLF / IF BAD LOAD FILE
2302 293C 98 TYA / OTHERWISE WE GOT A CIO ERROR
2303 293D 4C F6 31 JMP CIOER / GO SAY WHAT IT IS
2304 2940 A9 4D NLF LDA #.LOW.BLFL
2305 2942 A2 29 LDX #.LOW.BLFH
2306 2944 20 B5 31 JSR DSPLIN / BAD LOAD FILE MSG
2307 2947 20 AA 19 JSR CLOSX / CLOSE THE FILE
2308 294A 4C B6 20 LDFX JMP MENUCL / EXIT
2309 294D 42 41 44 20 BLF BYTE 'BAD LOAD FILE',CR
2310 2951 4C 4F 41 44
2311 2955 20 46 49 4C
2312 2959 45 9B
2313 295B
2314 0029 +BLFH = BLF
2315 004D +BLFL = (-256)*BLFH+BLF
2316 295B 4C 4F 41 44 LFMG BYTE 'LOAD FROM WHAT FILE?',CR
2317 295F 20 46 52 4F
2318 2963 4D 20 57 48
2319 2967 41 54 20 46
2320 296B 49 4C 45 3F
2321 296F 9B

```

2322

2323

2324

2325

2326 2970 85 29

2327 2972 20 CF 30

2328 2975 20 C4 30

2329 2978 A9 23

2330 297A A2 10

2331 297C 9D 42 03

2332 297F 20 EE 31

2333 2982 4C B6 20

2334 2985 57 48 41 54

2335 2989 20 46 49 4C

2336 298D 45 20 54 4F

2337 2991 20 4C 4F 43

2338 2995 4B 3F 9B

2339

2340 2998 AD 29

2341 299A 20 CF 30

2342 299D 20 C4 30

2343 29A0 A9 24

2344 29A2 A2 10

2345 29A4 9D 42 03

2346 29A7 20 EE 31

2347 29AA 4C B6 20

2348 29AD 57 48 41 54

2349 29B1 20 46 49 4C

2350 29B5 45 20 54 4F

2351 29B9 20 55 4E 4C

2352 29BD 4F 43 4B 3F

2353 29C1 9B

; **** LOCK & UNLOCK FILE COMMANDS ****

; LKFIL . WORD LKMG ; DO LOCK

JSR GETIC1

JSR PERX

LDA #LOCK

LDX #\$10

STA ICCOM, X

JSR CIOCL

JMP MENUSL

LKMG . BYTE 'WHAT FILE TO LOCK?', CR

; ULFIL . WORD ULMG ; DO UNLOCK

JSR GETIC1

JSR PERX

LDA #UNLOCK

LDX #\$10

STA ICCOM, X

JSR CIOCL

JMP MENUSL

ULMG . BYTE 'WHAT FILE TO UNLOCK?', CR

```

2354
2355
2356      ; ***** DUPLICATE DISK ROUTINE *****
2357      ;
2358      29C2  44 55 50 20      DDMMG      .BYTE      'DUP DISK-SOURCE,DEST DRIVES?',CR
2359      29C6  44 49 53 4B
2360      29CA  2D 53 4F 55
2361      29CE  52 43 45 2C
2362      29D2  44 45 53 54
2363      29D6  20 44 52 49
2364      29DA  56 45 53 3F
2365      29DE  9B
2366      29DF  54 59 50 45      OK          .BYTE      'TYPE ', $22, 'Y', $22, ' IF OK TO USE PROGRAM AREA', CR
2367      29E3  20 22 59 22
2368      29E7  20 49 46 20
2369      29EB  4F 4B 20 54
2370      29EF  4F 20 55 53
2371      29F3  45 20 50 52
2372      29F7  4F 47 52 41
2373      29FB  4D 20 41 52
2374      29FF  45 41 9B
2375      2A02
2376      0029
2377      00DF
2378      2A02  43 41 55 54
2379      2A06  49 4F 4E 3A
2380      2A0A  20 41 20 22
2381      2A0E  59 22 20 49
2382      2A12  4E 56 41 4C
2383      2A16  49 44 41 54
2384      2A1A  45 53 20 4D
2385      2A1E  45 4D 2E 53
2386      2A22  41 56 2E 9B
2387      2A26
2388      002A
2389      0002
2390
2391
2392
2393      2A26  A9 01
2394      2A28  8D 0B 03
2395      2A2B  A9 6B
2396      2A2D  8D 0A 03
2397      2A30  A9 1D
2398      2A32  8D 05 03
2399      2A35  A9 F4
2400      2A37  8D 04 03
2401      2A3A  20 8D 2C
2402      2A3D  A9 00
2403      2A3F  BD 01 1F
2404      2A42  AD FE 1D
2405      2A45  8D FE 1E
2406      2A48  A9 0B
2407      2A4A  BD 02 1F

      HILO      OK
      +OKH      =      OK/256
      +OKL      =      (-256)*OKH+OK
      CMSI      .BYTE      'CAUTION: A ', $22, 'Y', $22, ' INVALIDATES MEM. SAV. ', CR

      HILO      CMSI
      +CMSIH    =      CMSI/256
      +CMSIL    =      (-256)*CMSIH+CMSI

      ;
      ; RVTOC READS VOLUME TABLE OF CONTENTS SECTOR
      ;
      RVTOC     LDA      #1
                STA      DSHI          ; READ VTOC SECTOR
                LDA      #$6B
                STA      DSLO
                LDA      #.LOW.DBUFH
                STA      DBUFHI
                LDA      #.LOW.DBUFL
                STA      DBUFLO        ; POINT DCB AT DBUF
                JSR      RSEC1
                LDA      #0
                STA      PTR
                LDA      DBUF+$A
                STA      CSRC          ; BYTE OF ALLOC MAP
                LDA      #8
                STA      IPTR          ; COUNT BITS IN BYTE

```

```

2408 2A4D A9 00          LDA      #0
2409 2A4F 8D 0B 03      STA      DSHI          ; POINT TO SECTOR ONE
2410 2A52 A9 01          LDA      #1
2411 2A54 8D 0A 03      STA      DSLO
2412 2A57 60            RTS
2413
2414
2415 2A58 C2 29          DUPDSK  WORD    DDMG
2416 2A5A A9 00          LDA      #0          ; ASSUME SINGLE DRIVE
2417 2A5C 8D 0B 1F      STA      TWODRV      ; CLEAR FLAG
2418 2A5F 20 3C 30      JSR      GETLIN
2419 2A62 20 BE 32      JSR      GETDN
2420 2A65 8D F6 1E      STA      UNNO          ; UNIT NO FOR READ
2421 2A68 20 BE 32      JSR      GETDN
2422 2A6B 8D FF 1E      STA      CDES          ; CDES IS THE DEST DRIVE #
2423 2A6E 20 C4 30      JSR      PERX
2424
2425
2426
2427
2428
2429
2430 2A71 A9 80          LDA      ##80          ; ASSUME SOURCE IS 128 BYTE/SECTOR
2431 2A73 8D 0B 1F      STA      SECSIZ      ; SECSIZ IN LSB,MSB ORDER
2432 2A76 A9 00          LDA      #0
2433 2A78 8D 09 1F      STA      SECSIZ+1
2434
2435 2A7B AD F6 1E      LDA      UNNO          ; CHECK SOURCE FIRST, DO STATUS TEST
2436 2A7E 20 E4 2C      JSR      DRVSTAT      ; SETS CARRY IF 256, 128 THEN CARRY CLR
2437 2A81 90 09          BCC      ONE28          ; BRANCH IF 128 DEVICE
2438 2A83 A2 00          LDX      #0          ; ELSE SET SECSIZ AS 256 BYTES
2439 2A85 8E 0B 1F      STX      SECSIZ
2440 2A88 E8            INX
2441 2A89 8E 09 1F      STX      SECSIZ+1
2442
2443
2444
2445 2A8C AD FF 1E      ONE28  LDA      CDES          ; DO STATUS ON DEST
2446 2A8F 20 E4 2C      JSR      DRVSTAT
2447 2A92 90 0F          BCC      IS128          ; 128, YES TEST FOR 128 IN SECSIZ
2448 2A94 2C 0B 1F      BIT      SECSIZ      ; ELSE CHK FOR 256 IN SECSIZ
2449 2A97 10 0F          BPL      SAME          ; BRANCH IF DES & SRC ARE 256
2450
2451
2452
2453 2A99 A9 DE          INCOMP LDA      #.LOW.NCDRL      ; PRINT INCOMPATIBLE DRIVE
2454 2A9B A2 2A          LDX      #.LOW.NCDRH      ; MSG
2455 2A9D 20 B5 31      JSR      DSPLIN
2456 2AA0 4C B6 20      JMP      MENUSL          ; GOTO MENU
2457
2458
2459
2460 2AA3 2C 0B 1F      IS128  BIT      SECSIZ      ; IF LSB NOT 80 HEX THEN 256 SRC
2461 2AA6 10 F1          BPL      INCOMP          ; AND THEN INCOMPATIBLE

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 60

2462

2463

2464

2465 2AAB AD F6 1E

2466 2AAB CD FF 1E

2467 2AAE F0 4B

2468 2AB0 A2 2A

2469 2AB2 A9 BF

2470 2AB4 20 B5 31

2471 2AB7 20 7E 30

2472 2ABA CE 0B 1F

2473 2ABD 30 46

CHECK IF TWO DRIVE OR SINGLE DRIVE DUP

SAME

LDA UNNO

CMP CDES

BEG SDD

LDX #. LOW. IBDH

LDA #. LOW. IBDL

JSR DSPLIN

JSR CHRGET

DEC TWODRV

BMI DODKDP

IF BOTH UNITS THE SAME

SINGLE DRIVE DUP

PROMPT TO INSERT BOTH DISKS

SET TWO DRIVE FLAG

GO DUP DISK


```

2474
2475 2ABF 49 4E 53 45
2476 2AC3 52 54 20 42
2477 2AC7 4F 54 48 20
2478 2ACB 44 49 53 4B
2479 2ACF 53 2C 20 54
2480 2AD3 59 50 45 20
2481 2AD7 52 45 54 55
2482 2ADB 52 4E 9B
2483 2ADE
2484 002A
2485 00BF
2486 2ADE 45 52 52 4F
2487 2AE2 52 20 2D 20
2488 2AE6 44 52 49 56
2489 2AEA 45 53 20 49
2490 2AEE 4E 43 4F 4D
2491 2AF2 50 41 54 49
2492 2AF6 42 4C 45 2E
2493 2AFA 9B
2494 2AFB
2495 002A
2496 00DE
2497
2498
2499
2500
2501
2502
2503
2504 2AFB A9 16
2505 2AFD A2 2C
2506 2AFF 20 B5 31
2507 2B02 20 7E 30
2508 2B05 A9 05
2509 2B07 8D 06 1F
2510 2B0A A9 33
2511 2B0C 8D 07 1F
2512
2513
2514
2515
2516
2517
2518 2B0F AD E5 02
2519 2B12 3B
2520 2B13 ED 08 1F
2521 2B16 8D 04 1F
2522 2B19 AD E6 02
2523 2B1C ED 09 1F
2524 2B1F 8D 05 1F
2525
2526
2527

```

```

PAGE
IBD BYTE 'INSERT BOTH DISKS, TYPE RETURN',CR

```

```

HILO IBD
+IBDH = IBD/256
+IBDL = (-256)*IBDH+IBD
NCDR BYTE 'ERROR - DRIVES INCOMPATIBLE.',CR

```

```

HILO NCDR
+NCDRH = NCDR/256
+NCDRL = (-256)*NCDRH+NCDR

```

```

;
;
; USED BY BOTH SINGLE & DOUBLE DRIVE DUP. WILL NOT ASK TO SWAP IF 2 DRIVE
; FLAG (TWODRV) IS SET.
; IF THE TWO DRIVE FLAG IS CLEAR WILL
; FILL FROM SOURCE DISK, SWAP, EMPTY, SWAP, REPEAT.
;

```

```

SDD LDA #.LOW.ISDL ; TELL USER TO INSERT SOURCE
LDX #.LOW.ISDH ; FOR INITIAL READ - USED ONLY FOR SINGLE
JSR DSPLIN ; DRIVE DUPLICATE
JSR CHRGET
DODKDP LDA #.LOW.NMDUPL ; SET BUFFER AT END OF DUP
STA STVEC
LDA #.LOW.NMDUPH
STA STVEC+1

```

```

;
; BUFFER BOTTOM MOVES FROM NMDUP TO MEMTOP
; SET END OF BUFFER TO MEMTOP MINUS 1 SECTOR IN BYTES.
; WHEN BUFFER BOTTOM IS LESS THAN OR EQUAL TO BUFFER END, AT
; LEAST ONE MORE SECTOR WILL FIT IN MEMORY.
;

```

```

LDA MEMTOP
SEC
SBC SECSIZ ; T1 IS END OF BUFFER
STA T1
LDA MEMTOP+1
SBC SECSIZ+1
STA T1+1 ; T1 IS MEMTOP MINUS SECTOR SIZE.

```

```

;
; SEE IF ROOM FOR AT LEAST ONE SECTOR!
;

```

```

2528 2B22 AD 04 1F          LDA      T1              ; DO DOUBLE PRECISION TEST
2529 2B25 CD 06 1F          CMP      STVEC          ; TO SEE IF ROOM
2530 2B28 AD 05 1F          LDA      T1+1          ; IF T1 IS = STVEC THEN ENUF ROOM
2531 2B2B ED 07 1F          SBC      STVEC+1        ; FOR ONE SECTOR
2532 2B2E B0 0A              BCS      ENUF          ; BRANCH IF (T1)>=(STVEC)
2533 2B30 A9 06              NORM      LDA      #NRML
2534 2B32 A2 2C              LDX      #NRMH
2535 2B34 20 B5 31          JSR      DSPLIN
2536 2B37 4C B6 20          JMP      MENUSL
2537
2538 2B3A 20 BE 2C          ENUF      JSR      CKMEM          ; SEE IF OK TO USE USER AREA
2539 2B3D A9 00              LDA      #0
2540 2B3F 8D 9E 15          STA      OPT              ; SET UP FOR READ HERE FIRST PASS
2541 2B42 20 26 2A          JSR      RVTOC            ; READ VTOC
2542 2B45 AD 0A 03          LDA      DSLO            ; COPY INITIAL WRITE POINTERS
2543 2B48 8D F9 1E          STA      SWDP            ; TO INITIAL READ POINTERS
2544 2B4B AD 0B 03          LDA      DSHI
2545 2B4E 8D FA 1E          STA      SWDP+1
2546 2B51 AD 01 1F          LDA      PTR
2547 2B54 8D FB 1E          STA      SWDP+2
2548 2B57 AD 02 1F          LDA      IPTR
2549 2B5A 8D FC 1E          STA      SWDP+3
2550 2B5D AD FE 1E          LDA      CSRC
2551 2B60 8D FD 1E          STA      SWDP+4
2552 2B63 4C 7A 2B          JMP      LRS1              ; SKIP FIRST READ PROMPT
2553
2554                          ; READ FROM SOURCE DISK TIL BUF FULL OR END OF DATA.
2555
2556 2B66 A9 00              DORD      LDA      #0              ; FLAG WE ARE READING
2557 2B68 8D 9E 15          STA      OPT
2558 2B6B 2C 0B 1F          BIT      TWODRV          ; TEST FOR 2 DRIVES
2559 2B6E 30 0A              BMI      LRS1              ; YES, SKIP THE SWAP
2560 2B70 A9 16              LDA      # LOW. ISDL          ; INSERT SRC DISK
2561 2B72 A2 2C              LDX      # LOW. ISDH
2562 2B74 20 B5 31          XBLK      JSR      DSPLIN
2563 2B77 20 7E 30          JSR      CHRGET
2564
2565                          ; SWAP POINTERS TO WHERE WE ARE
2566
2567 2B7A 20 D2 2B          LRS1      JSR      DOSWDP          ; SWAP SECTOR AND BITMAP POINTERS
2568
2569                          ; LOOP READING/Writing SECTORS TO BUFFER AREA
2570
2571 2B7D 20 59 2C          LRS      JSR      AAM              ; ADVANCE ALLOCATION MAP
2572 2B80 30 21              BMI      ASPT              ; IF FREE, ADV SECTR POINTER & TRY AGIN
2573 2B82 2C 9E 15          BIT      OPT              ; SEE WHAT MODE
2574 2B85 30 06              BMI      DOW              ; BR IF WRITE
2575 2B87 20 8D 2C          JSR      RSEC1            ; DO READ
2576 2B8A 4C 90 2B          JMP      IOD
2577 2B8D 20 98 2C          DOW      JSR      DKWRT          ; DO WRITE
2578 2B90 AD 04 03          IOD      LDA      DBUFLO        ; ADVANCE BUFFER POINTER
2579 2B93 18              CLC
2580 2B94 6D 08 1F          ADC      SECSIZ          ; ADD SECTOR SIZE TO BOTTOM OF BUFFER
2581 2B97 8D 04 03          STA      DBUFLO          ; SO POINT TO NEXT FREE BLOCK

```

```

2582 2B9A AD 05 03      LDA      DBUFHI
2583 2B9D 6D 09 1F      ADC      SECSIZ+1
2584 2BA0 8D 05 03      STA      DBUFHI
2585 2BA3 20 76 2C      ASPT     JSR      ASP          ; GO ADVANCE SECTOR POINTER
2586 2BA6 F0 22          BEQ      STDD1      ; ALL SECTORS DONE, SWAP TO DEST DISK
2587 2BA8 AD 04 1F      LDA      T1          ; SEE IF ROOM FOR ANOTHER
2588 2BAB CD 04 03      CMP      DBUFLO      ; SECTOR BELOW MEMTOP
2589 2BAE AD 05 1F      LDA      T1+1
2590 2BB1 ED 05 03      SBC      DBUFHI
2591 2BB4 B0 C7          BCS      LRS          ; BRANCH IF (DBUF)<=(T1) - ROOM FOR MORE
2592
2593      ; SWAP DISKS AND CONTINUE
2594
2595 2BB6 AD 9E 15      STDD     LDA      OPT
2596 2BB9 30 AB          BMI      DORD          ; IF WAS WRITE, GO READ
2597 2BBB CE 9E 15      STDD2    DEC      OPT          ; CHANGE TO WRITE
2598 2BBE 2C 0B 1F      BIT      TWODRV      ; ARE 2 DRIVES BEING USED?
2599 2BC1 30 B7          BMI      LRS1         ; YES, SKIP THE SWAP
2600 2BC3 A9 35          LDA      #.LOW.IDDL    ; INSERT DEST DISK
2601 2BC5 A2 2C          LDX      #.LOW.IDDH
2602 2BC7 4C 74 2B      JMP      XBLK          ; GO DO WRITE
2603 2BCA AD 9E 15      STDD1    LDA      OPT          ; END OF DATA
2604 2BCD 10 EC          BPL      STDD2      ; IF READ GO WRITE
2605 2BCF 4C B6 20      JMP      MENUSL       ; IF WRITE WE ARE DONE
2606
2607      ; DOSWDP - EXCHANGE CURRENT AND SAVED BITMAP & SECTOR POINTERS
2608      ; ALSO INIT BUFFER POINTER
2609
2610 2BD2 A0 04          DOSWDP  LDY      #4
2611 2BD4 B9 FC 2B      SWLOP   LDA      SWATL, Y
2612 2BD7 85 1A          STA      RAMLO
2613 2BD9 B9 01 2C      LDA      SWATH, Y
2614 2BDC 85 1B          STA      RAMLO+1      ; GET ADDRESS FROM TABLE TO RAMLO
2615 2BDE A2 00          LDX      #0
2616 2BE0 A1 1A          LDA      (RAMLO, X)      ; GET WHAT'S THERE
2617 2BE2 4B            PHA
2618 2BE3 B9 F9 1E      LDA      SWDP, Y
2619 2BE6 81 1A          STA      (RAMLO, X)
2620 2BE8 6B            PLA
2621 2BE9 99 F9 1E      STA      SWDP, Y
2622 2BEC 8B            DEY
2623 2BED 10 E5          BPL      SWLOP
2624 2BEF AD 06 1F      LDA      STVEC
2625 2BF2 8D 04 03      STA      DBUFLO
2626 2BF5 AD 07 1F      LDA      STVEC+1
2627 2BF8 8D 05 03      STA      DBUFHI
2628 2BFB 60            RTS
2629
2630      ; WHAT A MESS
2631
2632 2BFC          HILO     DSLO
2633 0003          =        DSLO/256
2634 000A          =        (-256)*DSLOH+DSLO
2635 2BFC          HILO     DSHI

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 64

2636	0003	+DSHIH	=	DSHI/256
2637	000B	+DSHIL	=	(-256)*DSHIH+DSHI
2638	2BFC		HILO	PTR
2639	001F	+PTRH	=	PTR/256
2640	0001	+PTRL	=	(-256)*PTRH+PTR
2641	2BFC		HILO	IPTR
2642	001F	+IPTRH	=	IPTR/256
2643	0002	+IPTRL	=	(-256)*IPTRH+IPTR
2644	2BFC		HILO	CSRC
2645	001E	+CSRCH	=	CSRC/256
2646	00FE	+CSRCL	=	(-256)*CSRCH+CSRC

```

2647
2648 2BFC 0A 0B 01 02
2649 2C00 FE
2650 2C01 03 03 1F 1F
2651 2C05 1E
2652
2653
2654 2C06 4E 4F 54 20
2655 2C0A 45 4E 4F 55
2656 2C0E 47 48 20 52
2657 2C12 4F 4F 4D 9B
2658 2C16 49 4E 53 45
2659 2C1A 52 54 20 53
2660 2C1E 4F 55 52 43
2661 2C22 45 20 44 49
2662 2C26 53 4B 2C 54
2663 2C2A 59 50 45 20
2664 2C2E 52 45 54 55
2665 2C32 52 4E 9B
2666 2C35 49 4E 53 45
2667 2C39 52 54 20 44
2668 2C3D 45 53 54 49
2669 2C41 4E 41 54 49
2670 2C45 4F 4E 20 44
2671 2C49 49 53 4B 2C
2672 2C4D 54 59 50 45
2673 2C51 20 52 45 54
2674 2C55 55 52 4E 9B
2675 2C59
2676 002C
2677 0006
2678 2C59
2679 002C
2680 0016
2681 2C59
2682 002C
2683 0035
2684
2685
2686
2687
2688
2689 2C59 0E FE 1E
2690 2C5C 0E 02 1F
2691 2C5F D0 11
2692 2C61 EE 01 1F
2693 2C64 AE 01 1F
2694 2C67 BD FE 1D
2695 2C6A 8D FE 1E
2696 2C6D A9 0B
2697 2C6F 8D 02 1F
2698 2C72 AD FE 1E
2699 2C75 60
2700

```

```

; PAGE
SWATL . BYTE DSLOL, DSHIL, PTRL, IPTRL, CSRCL
;
SWATH . BYTE DSLOH, DSHIH, PTRH, IPTRH, CSRCH
;
;
NRM . BYTE 'NOT ENOUGH ROOM', CR
;
;
ISD . BYTE 'INSERT SOURCE DISK, TYPE RETURN', CR
;
;
IDD . BYTE 'INSERT DESTINATION DISK, TYPE RETURN', CR
;
;
HILO NRM
+NRMH = NRM/256
+NRML = (-256)*NRMH+NRM
HILO ISD
+ISDH = ISD/256
+ISDL = (-256)*ISDH+ISD
HILO IDD
+IDDH = IDD/256
+IDDL = (-256)*IDDH+IDD
;
;
; AAM - ADVANCE ALLOCATION MAP ONE BIT.
; RETURN MINUS IF FREE.
;
AAM ASL CSRC ; NEXT BIT OF ALLOC MAP
DEC IPTR
BNE CBIT ; IF DONE WITH THIS BYTE
INC PTR ; GET NEXT ONE
LDX PTR
LDA DBUF+*A, X ; VTOC IS DBUF & BITMAP STRTS IN 10TH BYT
STA CSRC
LDA #B
STA IPTR
CBIT LDA CSRC ; CHECK THE BIT
RTS
;

```

```

2701
2702
2703
2704 2C76 AD 0A 03
2705 2C79 C9 D0
2706 2C7B D0 07
2707 2C7D AD 0B 03
2708 2C80 C9 02
2709 2C82 F0 08
2710 2C84 EE 0A 03
2711 2C87 D0 03
2712 2C89 EE 0B 03
2713 2C8C 60
2714
2715
2716
2717 2C8D AD F6 1E
2718 2C90 8D 01 03
2719 2C93 18
2720 2C94 08
2721 2C95 4C A0 2C
2722
2723
2724
2725 2C98 AD FF 1E
2726 2C9B 8D 01 03
2727 2C9E 38
2728 2C9F 08
2729 2CA0 A9 02
2730 2CA2 8D F7 1E
2731 2CA5 A2 01
2732 2CA7 2C 0B 1F
2733 2CAA 30 01
2734 2CAC E8
2735 2CAD 28
2736 2CAE 08
2737 2CAF 20 72 07
2738 2CB2 10 08
2739
2740 2CB4 0E F7 1E
2741 2CB7 10 EC
2742 2CB9 4C F5 31
2743 2CBC 28
2744 2CBD 60
2745
2746
2747
2748 2CBE A5 08
2749 2CC0 F0 1C
2750 2CC2 A9 DF
2751 2CC4 A2 29
2752 2CC6 20 B5 31
2753 2CC9 A9 02
2754 2CCB A2 2A

; ASP - ADVANCE SECTOR POINTER IN DCB.
; RETURN EQ IF AT END.
ASP LDA DSLO ;SEE IF END
CMP #208
BNE NXS
LDA DSHI
CMP #2
BEQ ASPX ;ALL DONE
NXS INC DSLO
BNE ASPX
INC DSHI
ASPX RTS

; RSEC1 - READ A SECTOR WHOSE NUMBER IS IN DCB
RSEC1 LDA UNNO
STA DUNIT
CLC ;TELL DISK HANDLER DOING A GET SECTOR
PHP ;SAVE FLAG
JMP CLDKH

; DKWRT - WRITE A SECTOR
DKWRT LDA CDES ;PUT DEST UNIT #
STA DUNIT ;IN DCB
SEC ;TELL DISK HANDLER DOING WRITE SECTOR
PHP ;SAVE FLAG
CLDKH LDA #2 ;SET RETRY COUNT
STA RCNT
CLD1 LDX #1 ;SET DRIVE TYPE- ASSUME 128
BIT SECSIZ ;TEST FOR 128
BMI NOT256 ;IF IS BRANCH
INX ;ELSE SET FOR 256
NOT256 PLP
PHP ;SET ACTION FLAG & SAVE IT FOR RETRY
JSR BSIOR ;GOTO FMS DISK HANDLER
BPL DRTS ;RETURN IF GOOD STATUS

; ELSE SEE IF MORE RETRIES
BPL CLD1 ;YES, DO AGAIN
JMP CIOER1 ;CIO ERROR, GO SAY WHICH
DRTS PLP ;EVEN OUT STACK
RTS ;RETURN

; CKMEM - ASK IF OK TO USE USER AREA
CKMEM LDA WARMST ;IF MEMORY WAS INTACT
BEQ CPTR1 ;QUERY TO BOMB IT
LDA #.LOW.OKL
LDX #.LOW.OKH ;PRINT PROMPT
JSR DSPLIN
LDA #.LOW.CMSIL ;PRINT CAUTION MSG
LDX #.LOW.CMSIH ;Y RESPONSE WILL INVALIDATE MEM. SAV

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 27

```

2755 20CD 20 B5 31      JSR    DSPLIN
2756 20D0 20 7E 30      JSR    CHRGET
2757 20D3 C9 59          CMP    #'Y'          ; TEST FOR OK TO BOMB USER AREA
2758 20D5 D0 08          BNE    DDXT          ; IF SAY NO THEN DON'T DO DUP
2759 20D7 A9 00          LDA    #0
2760 20D9 85 08          STA    WARMST        ; TELL CART NO GOOD USER MEMORY
2761 20DB 8D 9E 17      STA    MEMFLG        ; TELL LOADER NO GOOD MEM. SAV
2762 20DE 60              CPTR1  RTS
2763
2764 20DF 68              DDXT   PLA          ; POP RETURN ADDRESS
2765 20E0 68              PLA
2766 20E1 4C B6 20      JMP     MENU5L        ; GOTO MENU, DON'T DO DUP
2767
2768
2769
2770
2771
2772
2773
2774 20E4 8D 01 03      DRVSTAT STA DUNIT        ; STORE UNIT NUMBER IN DCB
2775 20E7 A9 53          LDA    #STAREQ      ; STORE STATUS COMMAND IN DCB
2776 20E9 8D 02 03      STA    DCOMND
2777 20EC A9 02          LDA    #2          ; SET RETRY COUNT
2778 20EE 8D F7 1E      STA    RCNT
2779 20F1 20 53 E4      DOSTAT JSR    DKHND        ; DO STATUS WITH OS HANDLER
2780 20F4 10 08          BPL    CHK1YP      ; IF GOOD RETURN, DETERMINE TYPE
2781
2782 20F6 CE F7 1E          DEC    RCNT        ; ELSE SEE IF ANOTHER RETRY
2783 20F9 10 F6          BPL    DOSTAT      ; YES, DO AGAIN
2784 20FB 4C F5 31      JMP     CIDER1      ; ELSE ERROR EXIT
2785
2786 20FE 18              CHK1YP CLC          ; ASSUME 128 BYTE DEVICE
2787 20FF AD EA 02      LDA    DVSTAT        ; GET COMMAND STATUS BYTE
2788 2D02 29 20          AND    ##20        ; MASK FOR DRIVE TYPE BIT-- D5
2789 2D04 F0 01          BEQ     RETSTAT      ; 128 IF = 0
2790 2D06 38              SEC          ; 256 IF = 1
2791 2D07 60              RETSTAT RTS
2792
2793
2794
2795
2796
2797
2798
2799
2800
2801
2802
2803
2804
2805
2806
2807
2808

```

***** DUPLICATE FILE COMMAND *****
 ;
 ;
 ; DUPLICATE FILE FROM ONE DISK TO ANOTHER
 ; USING ONE DRIVE. FILENAME FOR DUPLICATE FILE IS SAME AS
 ; SOURCE NAME. USER CAN ENTER ONLY THE SOURCE FILE SPECIFICATION.
 ; USER HAS OPTION OF USING PROGRAM AREA FOR COPY OR A 250 BYTE
 ; DATA BUFFER TO GET PROGRAM AREA USER MUST RESPOND WITH
 ; 'Y' AS 1ST CHAR OR THEY WILL GET THE DATA BUFFER. WILL DUPLICATE
 ; FILE OF ANY SIZE. IF ERROR, PRINTS MSG, CLOSES FILE(S) OPEN AND
 ; RETURNS TO MENU. TO PREVENT POSSIBLE DAMAGE TO DESTINATION
 ; DISK, FILE IS OPENED AND CLOSED FOR EACH WRITE.
 ; MAKES BUFR LEN AN EVEN MULTIPLE OF 125. THIS PREVENTS FRAGMENTATION
 ; OF THE FILE DUE TO THE APPEND OPEN FUNC. 125 IS USED BECAUSE IT IS THE
 ; SIZE OF DATA PORTION IN A SECTOR. IF THIS CHANGES THE VALUE IN THE PGM
 ; MUST BE CHANGED.
 ; K. B. 5/7/80

```

DPFM      BYTE      'NAME OF FILE TO MOVE?',CR

;
;
;
DUPFIL     WORD      DPFM              ; DUPLICATE FILE PROMPT
JSR        GETIC1          ; GET FILENAME TO DUPLICATE ON SAME DRIVE
JSR        PERX            ; DON'T COME BACK IF PARAMETER ERRORS
LDA        PAR
CMP        #'D             ; DUPLICATE FILE ONLY FOR DISK DEVICE
BEQ        ISDISK
JMP        ODMS            ; IF NOT -- SAY CANNOT DO & EXIT

;
ISDISK     JSR          USEPGM         ; ASK USER IF TO USE PROG AREA OR BUFFER
;
;       HAVE USER INSERT SOURCE FILE AND HIT <CR> WHEN DONE
;
LDX        #LOW.ISDH       ; ARG: LINE TO BE DISPLAYED ADDR
LDA        #LOW.ISDL       ; IN REG. A & X
JSR        DSPLIN          ; PRINT INSERT SOURCE MSG
JSR        GETLIN          ; GOTO SCREEN & WAIT FOR <CR>
JSR        PERX            ; GOTO MENU IF BREAK KEY HIT

;
JSR        LOOKWC          ; SEE IF FILE SPEC. USES WILDCARDS
BNE        NOWC            ; BRANCH IF NO WILD CARDS USED - USE OLD
LDA        #$40            ; SET 'DUPLICATE WILDCARD' MODE
JMP        WCINIT          ; OPEN WILDCARD DIRECTORY FILE, ETC.

NOWC       =          *

;
;       MAKE SURE DEST NOT DOS.SYS
;
LDX        #0              ; ENTRY-INDEX TO FIRST CHAR OF FILE NAME
JSR        TSTDOS          ; WON'T RETURN IF IS DOS.SYS

;
;       OPEN SOURCE FILE - ADDR OF FILENAME STRING IN PARAM LIST IS
;       ALREADY ASSIGNED TO IOCB # 2
;
WCDUPS     LDX          ##10          ; USE IOCB #2
LDA        #OPEN           ; OPEN COMMAND
STA        ICCOM,X
LDA        #4              ; READ ONLY
STA        ICAX1,X
JSR        CIDCL           ; CALL CIO - IF ERR PRNT MSG,CLOSE, GOTO

; EOFFLG - SOURCE FILE EOF FLAG   FTRF - FLAG TO SHOW IF 1ST TIME SOURCE
; FILE WAS READ
;
LDA        #0
STA        EOFFLG          ; CLEAR EOF FLAG
STA        FTRF            ; CLEAR MEANS FIRST TIME

```



```

2863
2864
2865
2866
2867
2868 2D66 A2 10
2869 2D68 A5 1A
2870 2D6A 9D 44 03
2871 2D6D A5 1B
2872 2D6F 9D 45 03
2873 2D72 AD 04 1F
2874 2D75 9D 48 03
2875 2D78 AD 05 1F
2876 2D7B 9D 49 03
2877 2D7E A9 07
2878 2D80 9D 42 03
2879 2D83 20 56 E4
2880
2881
2882
2883
2884 2D86 10 0A
2885 2D88 C0 88
2886 2D8A F0 03
2887 2D8C 4C F5 31
2888 2D8F CE 0A 1F
2889
2890
2891
2892
2893 2D92 A2 2C
2894 2D94 A9 35
2895 2D96 20 B5 31
2896 2D99 20 3C 30
2897 2D9C 2C F5 1E
2898 2D9F 10 03
2899 2DA1 4C 1F 2E
2900
2901
2902
2903
2904 2DA4 A2 20
2905 2DA6 A0 09
2906 2DAB AD 0B 1F
2907 2DAB D0 05
2908 2DAD A0 08
2909 2DAF EE 0B 1F
2910
2911 2DB2 98
2912 2DB3 9D 4A 03
2913 2DB6 A9 03
2914 2DB8 9D 42 03
2915
2916

```

```

;
; DO UNTIL (SOURCE EOF FLAG (EOFFLG) IS SET)
; SET UP IOCB#2 TO DO GET CHAR.  ZP LOC BUFADR HAS BUFFER ADDRESS
; BUFLN HAS BUFFER LENGTH
;
DODUP LDX    ##10          ;USE IOCB #2
      LDA    BUFADR        ;IN LSB,MSB ORDER
      STA    ICBAL,X       ;SET BUFFER ADDR IN IOCB #2
      LDA    BUFADR+1
      STA    ICBAL,X
      LDA    BUFLN         ;IN LSB,MSB ORDER
      STA    ICBLL,X       ;STORE BUFFER LENGTH
      LDA    BUFLN+1       ;IN IOCB #2
      STA    ICBLL,X
      LDA    #GETCHR       ;COMMAND TO GET CHAR - IGNORE EOL'S (9B)
      STA    ICCOM,X
      JSR    CIO           ;CALL CIO
;
; CHECK FOR ENDFILE. IF YES, THEN SET FLG. CHECK FOR ERR. IF ERR
; THEN PRINT MSG, CLOSE FILE, AND RETURN TO MENU.
;
      BPL    INSDDES       ;IF GOOD READ WRITE BUFFER
      CPY    #EOF          ;WAS IT EOF?
      BEQ    SETFLG        ;YES, THEN SET FLAG
      JMP    CIOERR1       ;WAS ERR - PRINT MSG, CLOSE, GOTO MENU
SETFLG DEC    EOFLG        ;SET ENDFILE FLAG
;
; WHEN GOOD READ OR EOF GET HERE. ASK USER TO INSERT DESTINATION
; DISK AND ATTEMPT TO WRITE TO DESTINATION FILE.
;
INSDDES LDX    #.LOW.IDDH   ;ARG: ADDRESS OF LINE TO BE PRINTED
      LDA    #.LOW.IDDL   ;IN REGS A AND X
      JSR    DSPLIN       ;SAY TO SWAP DISKS
      JSR    GETLIN       ;WAIT TIL USER HITS <CR>
      BIT    PER          ;WAS BREAK KEY HIT?
      BPL    DODEST       ;NO, TRY WRITE
      JMP    CLSSRC       ;YES, CLOSE & GOTO MENU
;
; CHECK IF FIRST TIME SRC WAS READ. IF YES, THEN OPEN FOR OUTPUT
; ONLY. OTHERWISE, OPEN FOR OUTPUT APPEND.
;
DODEST LDX    ##20          ;USE IOCB #3 FOR DESTINATION
      LDY    #9           ;ASSUME APPEND
      LDA    FTRF         ;IS FLAG CLEAR?
      BNE    OPNDES       ;NO,NOT FIRST TIME - OPEN APPEND
      LDY    #8           ;YES, THEN OPEN OUT ONLY
      INC    FTRF         ;SET TO SHOW NOT FIRST TIME NEXT TIME
;
OPNDES TYA
      STA    ICAX1,X      ;SET AUX1 BYTE
      LDA    #OPEN        ;OPEN COMMAND
      STA    ICCOM,X
;
; THE FILENAME IS THE FIRST FILE IN THE PARAMETER LIST-PAR.

```

```

2917
2918 2DBB A9 7C          LDA    #PARL          ;SET BUFR ADDR TO FILE SPEC TO BE OPENED
2919 2DDD A0 1D          LDY    #PARH
2920 2DBF 2C 41 23       BIT     WCFLAG          ; IF WLDCARD-WLDCARD BUFR INSTEAD OF PAR
2921 2DC2 50 04          BVC     SKIPWC
2922
2923 2DC4 A9 64          LDA    #.LOW.WCBUF2
2924 2DC6 A0 23          LDY    #.HIGH.WCBUF2
2925
2926 2DC8 9D 44 03       SKIPWC STA    ICBAL,X
2927 2DCB 98             TYA
2928 2DCC 9D 45 03       STA    ICBAH,X
2929 2DCF 20 EE 31       JSR     CIOCL          ;CALL CIO, IF ERROR GOTO MENU
2930
2931                     ,
2932                     ; CHECK IF SOURCE BUFR LEN IS NOT EQUAL TO ZERO. IF NOT = ZERO
2933                     ; THEN WRITE BUFFER TO THE DESTINATION FILE.
2934 2DD2 A0 10          LDY    ##10          ;SOURCE IS AT IOCB #2
2935 2DD4 A2 20          LDX    ##20          ;DEST IS AT IOCB #3
2936 2DD6 A9 00          LDA    #0           ;CHECK LENGTH LOW FOR ZERO
2937 2DD8 D9 48 03       CMP     ICBLL,Y      ;LOW=0
2938 2DDB D0 05          BNE     DOWRIT       ;NO THEN WRITE BUFFER
2939 2DDD D9 49 03       CMP     ICBLH,Y      ;IS HI=0?
2940 2DE0 F0 1E          BEQ     CLSDES       ;YES, DON'T WRITE EMPTY BUFFER
2941
2942 2DE2 A9 0B          DOWRIT LDA    #PUTCHR      ;PUT CHAR COMMAND CODE
2943 2DE4 9D 42 03       STA    ICCOM,X      ;IGNORE EOLS (9B)
2944 2DE7 A5 1A          LDA    BUFADR       ;GET BUFFER ADDRESS
2945 2DE9 9D 44 03       STA    ICBAL,X
2946 2DEC A5 1B          LDA    BUFADR+1
2947 2DEE 9D 45 03       STA    ICBAH,X
2948 2DF1 B9 48 03       LDA    ICBLL,Y      ;GET BUFFER LENGTH TO WRITE
2949 2DF4 9D 48 03       STA    ICBLL,X      ;FROM IOCB OF SOURCE FILE
2950 2DF7 B9 49 03       LDA    ICBLH,Y      ;SET BY GET TO ACTUAL BYTE
2951 2DFA 9D 49 03       STA    ICBLH,X      ;COUNT READ INTO BUFFER
2952 2DFD 20 EE 31       JSR     CIOCL       ;DO WRITE - IF ERR GOTO MENU
2953
2954                     ; CLOSE DESTINATION FILE
2955
2956 2E00 A9 0C          CLSDES LDA    #CLOSE      ;CLOSE COMMAND CODE
2957 2E02 9D 42 03       STA    ICCOM,X      ;CALL CIO - IF ERROR GOTO
2958 2E05 20 EE 31       JSR     CIOCL       ;MENU AFTER PRINT MSG
2959
2960                     ; TEST ENDFILE FLAG. IF IT IS SET THEN COMPLETED DUPLICATION.
2961                     ; OTHERWISE, DO LOOP BODY AGAIN (READ THEN WRITE).
2962
2963 2E08 AD 0A 1F       LDA    EOFLG        ;IS SOURCE AT ENDFILE?
2964 2E0B D0 12          BNE     CLSSRC       ;YES, THEN DONE
2965
2966                     ; ASK USER TO INSERT SOURCE FOR NEXT READ & THEN REPEAT LOOP
2967
2968 2E0D A2 2C          LDX    #.LOW.ISDH     ;ARGS: ADDRESS OF LINE TO PRINT IN
2969 2E0F A9 16          LDA    #.LOW.ISDL     ;REGS A AND X
2970 2E11 20 B5 31       JSR     DSPLIN       ;SAY TO INSERT SOURCE

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 71

```

2971 2E14 20 3C 30      JSR      GETLIN      ;WAIT TIL USER HITS <CR>
2972 2E17 2C F5 1E      BIT      PER        ;WAS BREAK KEY HIT?
2973 2E1A 30 03      BMI      CLSSRC     ;YES, CLOSE & GOTO MENU
2974 2E1C 4C 66 2D      JMP      DDDUP      ;REPEAT LOOP
2975
2976
2977      ; *****END OF LOOP*****
2978      ;
2979      ; CLOSE SOURCE AND RETURN TO MENU
2980 2E1F A2 10      CLSSRC LDX      #$10      ;SOURCE AT IOCB #2
2981 2E21 A9 0C      LDA      #CLOSE     ;CLOSE COMMAND CODE
2982 2E23 9D 42 03      STA      ICCOM,X
2983 2E26 20 56 E4      JSR      CIO        ;CALL CIO
2984
2985 2E29 2C 41 23      BIT      WCFLAG     ;TEST IF 'DUPLICATE WILDCARD' MODE
2986 2E2C 50 10      BVC      DUFFEX     ;BR IF NOT 'DUPLICATE WILDCARD' MODE
2987 2E2E A2 2C      LDX      #.LOW.ISDH ;INSERT SOURCE MESSAGE
2988 2E30 A9 16      LDA      #.LOW.ISDL
2989 2E32 20 B5 31      JSR      DSPLIN     ;NEEDED TO GET NEXT WILDCARD DIR ENTRY
2990 2E35 20 3C 30      JSR      GETLIN     ;WAIT FOR CR
2991 2E38 20 C4 30      JSR      PERX       ;IF BREAK-KEY ABORT - EXIT TO MENU
2992 2E3B 4C 9E 23      JMP      WCOPYL     ;JUMP TO WILDCARD LOOP
2993 2E3E
2994
2995 2E3E 4C B6 20      DUPFEX =      *
      ;
      ; JMP      MENUSL      ;GO TO THE MENU

```

2996

2997

2998

2999

3000

3001

3002

3003

3004

3005

3006

3007

3008 2E41 A5 08

3009 2E43 F0 15

3010 2E45 A9 DF

3011 2E47 A2 29

3012 2E49 20 B5 31

3013 2E4C A9 02

3014 2E4E A2 2A

3015 2E50 20 B5 31

3016 2E53 20 7E 30

3017 2E56 C9 59

3018 2E58 D0 6A

3019

3020

3021

3022

3023 2E5A A9 00

3024 2E5C B5 08

3025 2E5E 8D 9E 17

3026 2E61 A9 05

3027 2E63 B5 1A

3028 2E65 A9 33

3029 2E67 B5 1B

3030 2E69 AD E5 02

3031 2E6C 38

3032 2E6D E9 05

3033 2E6F 8D 04 1F

3034 2E72 AD E6 02

3035 2E75 E9 33

3036 2E77 8D 05 1F

3037

3038

3039

3040

3041

3042 2E7A A9 00

3043 2E7C 8D 06 1F

3044 2E7F 8D 07 1F

3045

3046

3047

3048 2E82 A9 7D

3049 2E84 18

PAGE

**** ASK IF OK TO USE PROGRAM AREA ROUTINE ****

ASK USER IF CAN USE PROGRAM AREA. IF SAY YES ('Y') THEN
 ASSIGN BUFFER ADDRESS AS ALL AVAILABLE MEMORY. OTHERWISE, USE
 DBUF (250 BYTES) AS THE BUFFER. ASSIGNS BUFFER LENGTH.

NO PARAMETERS

RETURNS: BUFADR-BUFFER ADDRESS

BUFLEN-BUFFER LENGTH

```

USEPGM LDA WARMST      ; CHECK IF PGM AREA ALREADY
      BEQ USED84      ; USED-YES, USE IT AGAIN
      LDA #.LOW.OKL   ; ARGS: IN A AND X ADDR
      LDX #.LOW.OKH   ; OF LINE TO DISPLAY
      JSR DSPLIN      ; ASK TO USE PGM AREA
      LDA #.LOW.CMSIL ; SAY A Y RESPONSE WILL
      LDX #.LOW.CMSIH ; INVALIDATE MEM.SAV
      JSR DSPLIN      ; PRINT CAUTION
      JSR CHRGET      ; GET 1ST CHAR OF
      CMP #'Y         ; USERS RESPONSE
      BNE USEBUF      ; NO, THEN USE DBUFF
  
```

USE ALL MEMORY AVAILABLE-PROGRAM AREA

MEMLO, MEMTOP, BUFADR, BUFLN ARE IN LSB, MSB FORM

```

USED84 LDA #0          ; CLEAR WARMSTART FLAG
      STA WARMST      ; TO SHOW PGM AREA USED
      STA MEMFLG      ; SHOW NO USER AREA GOOD-MEM.SAV ALSO
      LDA #.LOW.NMDUPL ; USE ALL AVAILABLE
      STA BUFADR      ; MEMORY-FROM END OF DUP TO MEMTOP
      LDA #.LOW.NMDUPH ; BUFADR HAS BUFFER
      STA BUFADR+1    ; ADDRESS
      LDA MEMTOP      ; GET LENGTH OF
      SEC             ; PGM AREA
      SBC #.LOW.NMDUPL
      STA BUFLN       ; LSB, MSB ORDER
      LDA MEMTOP+1
      SBC #.LOW.NMDUPH
      STA BUFLN+1
  
```

FIND THE GREATEST MULTIPLE OF 125 LESS THAN THE PROGRAM AREA
 THEN SET BUFR LEN TO IT. THIS PREVENTS FRAGMENTATION TO FILE
 WHEN APPEND IS USED IN DUPFIL.

```

LDA #0          ; INIT MULTIPLE OF 125 (MLT125) TO ZERO
STA MLT125
STA MLT125+1
  
```

DO UNTIL (MLT125 > BUFLN)

```

FINDGM LDA #125      ; INC THE MULTIPLE OF 125 BY 125
      CLC             ; TO GET THE NEXT HIGHER MULTIPLE
  
```

```

3050 2E85 6D 06 1F      ADC      MLT125
3051 2E88 8D 06 1F      STA      MLT125
3052 2E8B A9 00      LDA      #0
3053 2E8D 6D 07 1F      ADC      MLT125+1      ; MLT125 IS IN LSB,MSB ORDER
3054 2E90 8D 07 1F      STA      MLT125+1
3055
3056      ;
3057      ; TEST FOR MLT125 > BUFLN - LOOP TEST
3058 2E93 AD 05 1F      LDA      BUFLN+1      ; IS MSB OF MLT125 > MSB OF BUFLN?
3059 2E96 CD 07 1F      CMP      MLT125+1
3060 2E99 90 0A      BCC      GETMLT      ; YES, THEN END LOOP
3061 2E9B D0 E5      BNE      FINDGM      ; IF MLT<BUFLN, REPEAT LOOP
3062 2E9D AD 04 1F      LDA      BUFLN      ; ELSE MSB'S ARE =. CHECK THE LSB'S.
3063 2EA0 CD 06 1F      CMP      MLT125      ; IS LSB MLT125 > LSB BUFLN?
3064 2EA3 B0 DD      BCS      FINDGM      ; NO, REPEAT LOOP
3065      ;
3066      ; ***** END OF LOOP*****
3067      ;
3068      ; CHECK IF MULTIPLE = TO 125. IF IS, THEN LEAVE BUFLN AS IS. IF
3069      ; ISN'T THEN SET BUFLN TO THAT MULTIPLE OF 125 MINUS 125.
3070      ;
3071 2EA5 AD 07 1F      GETMLT LDA      MLT125+1      ; IS MSB NOT = ZERO?
3072 2EA8 D0 08      BNE      REPLAC      ; YES, VALUE IS > 125
3073 2EAA A9 7D      LDA      #125      ; IS LSB > 125?
3074 2EAC CD 06 1F      CMP      MLT125
3075 2EAF 90 01      BCC      REPLAC      ; YES, REPLACE BUFLN WITH MLT125
3076 2EB1 60      RTS      ; ELSE LEAVE BUFLN AS IS
3077      ;
3078 2EB2 AD 06 1F      REPLAC LDA      MLT125      ; SUBTRACT 125 FROM MLT125 TO GET
3079 2EB5 38      SEC      ; GREATEST MULTIPLE LESS THAN OR EQUAL
3080 2EB6 E9 7D      SBC      #125      ; TO THE PROGRAM AREA.
3081 2EB8 8D 04 1F      STA      BUFLN      ; USE IT AS THE BUFFER LENGTH.
3082 2EBB AD 07 1F      LDA      MLT125+1
3083 2EBE E9 00      SBC      #0
3084 2EC0 8D 05 1F      STA      BUFLN+1
3085 2EC3 60      RTS      ; RETURN
3086      ;
3087      ; USE BUFFER DBUF (250 BYTES) INSTEAD OF PROGRAM AREA
3088      ;
3089 2EC4 A9 F4      USEBUF LDA      #.LOW.DBUFL      ; USE DBUF AS
3090 2EC6 85 1A      STA      BUFADR      ; BUFFER ADDRESS
3091 2EC8 A9 1D      LDA      #.LOW.DBUFH      ; IN LSB,MSB ORDER
3092 2ECA 85 1B      STA      BUFADR+1
3093 2ECC A9 FA      LDA      #EDBL      ; STORE DATA
3094 2ECE 8D 04 1F      STA      BUFLN      ; BUFFER LENGTH
3095 2ED1 A9 00      LDA      #EDBLH      ; =TO 256(100HEX)
3096 2ED3 8D 05 1F      STA      BUFLN+1      ; IN LSB,MSB ORDER
3097 2ED6 60      RTS      ; RETURN

```

3098
 3099
 3100
 3101
 3102
 3103
 3104
 3105
 3106 2ED7 BD 7C 1D
 3107 2EDA E8
 3108 2EDB C9 2A
 3109 2EDD F0 0D
 3110 2EDF C9 3F
 3111 2EE1 F0 09
 3112 2EE3 C9 9B
 3113 2EE5 F0 04
 3114 2EE7 C9 2C
 3115 2EE9 D0 EC
 3116
 3117 2EEB E8
 3118 2EEC 60

```

PAGE
**** CHECK FILENAME FOR WILDCARD CHARACTERS ****

CHECKS THE STRING AT PAR,X FOR WILDCARD CHARACTERS (* OR ?). IF
THEY ARE FOUND THE ROUTINE SETS THE = FLAG. IF A <CR> IS FOUND
RETURNS TO THE CALLING ROUTINE WITH THE EQUAL FLAG RESET.

LOOKWC LDA    PAR,X
        INX
        CMP    #'*
        BEQ    LOOKW2
        CMP    #'?
        BEQ    LOOKW2
        CMP    #CR
        BEQ    LOOKW1
        CMP    #',
        BNE    LOOKWC
; TERMINATE WITH CR OR COMMA

LOOKW1 INX
LOOKW2 RTS
  
```

```

3119          .PAGE
3120          **** TEST FILE SPEC FOR DOS.SYS ****
3121
3122
3123          SUBROUTINE - TSTDOS
3124
3125          CHECKS A FILE SPEC IN THE STORAGE LOC FOR DOS.SYS.  USED TO
3126          PREVENT COPYING TO A FILE NAMED DOS.SYS.  IF DOS.SYS IS OPENED
3127          OUTPUT FMS WILL WRITE A COPY OF DOS OUT TO THE FILE.
3128
3129          ENTRY - REG X HAS INDEX INTO PAR TO FIRST CHAR OF FILE SPEC
3130                  ASSUMES COMPLETE FILE SPEC.
3131          EXIT - WILL NOT RETURN IF FILE NAME = DOS.SYS, BUT GOES TO MENU
3132
3133          FIND END OF DEVICE ID - COLON
3134
3135          TSTDOS INX          ;NEVER IS FIRST CHAR
3136          2EED   EB          LDA    PAR,X          ;GET 2ND CHAR
3137          2EEE   BD 7C 1D    CMP    #'          ;IS IT A COLON?
3138          2EF1   C9 3A      BEQ    GOTCOL         ;YES, THEN NAME STARTS AT CHAR 3
3139          2EF3   F0 01      INX          ;ELSE NAME STARTS AT CHAR 4
3140          2EF5   EB          GOTCOL INX          ;POINT AT FIRST CHAR OF NAME
3141
3142          ;
3143          COMPARE FILE NAME IN PAR WITH DOS.SYS
3144
3145          LDY    #0          ;INDEX INTO DOS.SYS FILE SPEC
3146
3147          NXTCHAR LDA    DS+3,Y      ;GET NEXT DOS.SYS CHAR
3148          2EF9   B9 CD 2B    CMP    PAR,X          ;TEST IF FILE NAME IS SAME
3149          2EFC   DD 7C 1D    BNE    NOTSAM         ;NO, THEN RETURN
3150          2EFF   D0 10      INY
3151          2F01   C8          INX          ;ELSE TRY NEXT CHAR
3152          2F02   EB          CPY    #7          ;ARE THERE MORE CHARS TO TRY?
3153          2F03   C0 07      BNE    NXTCHAR        ;YES, DO AGAIN
3154          2F05   D0 F2
3155
3156          ;
3157          FILE NAME EQUALS DOS.SYS - ERROR EXIT
3158
3159          LDA    #.LOW.DCDSL      ;PRINT MSG - DEST CAN'T BE DOS.SYS
3160          LDX    #.LOW.DCDSH
3161          JSR    DSPLIN
3162          JMP    MENUSL          ;GOTO MENU
3163
3164          ;
3165          NOT EQUAL TO DOS.SYS - RETURN TO CALLER
3166
3167          NOTSAM RTS
3168
3169          ;
3170          DCDS .BYTE 'DESTINATION CANT BE DOS.SYS',CR
3171
3172          HILO    DCDS

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 74

3173 002F

+DCDSH =

DCDS/256

3174 0012

+DCDSL =

(-256)*DCDSH+DCDS


```

3175                                     PAGE
3176                                     **** SAVE FILE ROUTINE ****
3177
3178
3179 2F2E 18 30 SAVFIL WORD SFMG
3180 2F30 A9 00 LDA #0
3181 2F32 8D A0 18 STA INITQ+1
3182 2F35 8D BE 18 STA RUNQ+1
3183 2F38 20 CF 30 JSR GETIC1
3184 2F3B AD 9E 15 LDA OPT
3185 2F3E 48 PHA
3186 2F3F AE 01 1F LDX PTR ; PUT EOL ON FILENAME
3187 2F42 A9 9B LDA #CR
3188 2F44 9D 7B 1D STA PAR-1, X
3189 2F47 20 24 32 JSR GETNO ; GET HEX PARAMETER
3190 2F4A 8D E0 19 STA LDST
3191 2F4D 8E E1 19 STX LDST+1
3192 2F50 E0 32 CPX #. LOW. NDSH
3193 2F52 B0 03 BCS DSLMFG ; BRANCH IF NOT SAVING DUP AREA
3194 2F54 CE 94 18 DEC WDR1+1
3195 2F57 20 24 32 DSLMFG JSR GETNO ; END ADDRESS
3196 2F5A 8D E2 19 STA LDND
3197 2F5D 8E E3 19 STX LDND+1
3198 2F60 3B SEC
3199 2F61 ED E0 19 SBC LDST
3200 2F64 8D F8 2F STA WDR1+1
3201 2F67 8A TXA
3202 2F68 ED E1 19 SBC LDST+1
3203 2F6B 10 03 BPL ADDOK ; BR IF ENDING ADDR > THAN STARTING
3204 2F6D 4C B6 20 JMP MENU ; ELSE BACK TO MENU
3205 2F70 8D FD 2F ADDOK STA WDRH+1
3206 2F73 C0 9B CPY #CR
3207 2F75 F0 29 BEQ NRUNAD ; BRANCH IF NO MORE PARAMS
3208 2F77 20 24 32 JSR GETNO ; GET A RUN ADDRESS IF ANY
3209 2F7A 8D E2 02 STA INITAD
3210 2F7D 8E E3 02 STX INITAD+1
3211 2F80 0D E3 02 ORA INITAD+1
3212 2F83 F0 03 BEQ NINTAD ; BRANCH IF NO INIT ADDRESS GIVEN
3213 2F85 CE A0 18 DEC INITQ+1 ; SET FLAG
3214 2F88 C0 9B NINTAD CPY #CR
3215 2F8A F0 14 BEQ NRUNAD ; BRANCH IF NO RUN ADDRESS GIVEN
3216 2F8C 20 24 32 JSR GETNO ; GET RUN ADDRESS
3217 2F8F 20 C4 30 JSR PERX ; CHECK FOR ERRORS
3218 2F92 8D E0 02 STA RUNAD
3219 2F95 8E E1 02 STX RUNAD+1
3220 2F98 0D E1 02 ORA RUNAD+1
3221 2F9B F0 03 BEQ NRUNAD ; BRANCH IF NO RUN ADDRESS
3222 2F9D CE BE 18 DEC RUNQ+1 ; SET FLAG
3223 2FA0 A9 00 NRUNAD LDA #0
3224 2FA2 8D 9E 15 STA OPT
3225 2FA5 6B PLA ; OPTION CHAR FROM FILENAME
3226 2FA6 C9 41 CMP #'A ; IF APPEND
3227 2FAB D0 03 BNE **5
3228 2FAA CE 9E 15 DEC OPT ; SET OT=0FF

```

```

3229
3230
3231
3232 2FAD A2 10
3233 2FAF A9 03
3234 2FD1 9D 42 03
3235 2FB4 2C 9E 15
3236 2FB7 30 04
3237 2FB9 A9 08
3238 2FBB D0 02
3239 2FBD A9 09
3240 2FBF 9D 4A 03
3241 2FC2 20 EE 31
3242
3243
3244
3245 2FC5 A9 0B
3246 2FC7 9D 42 03
3247 2FCA A9 DE
3248 2FCC 9D 44 03
3249 2FCF A9 19
3250 2FD1 9D 45 03
3251 2FD4 A9 06
3252 2FD6 9D 48 03
3253 2FD9 A9 00
3254 2FDB 9D 49 03
3255 2FDE 2C 9E 15
3256 2FE1 10 0F
3257 2FE3 A9 04
3258 2FE5 9D 48 03
3259 2FE8 A9 E0
3260 2FEA 9D 44 03
3261 2FED A9 19
3262 2FEF 9D 45 03
3263 2FF2 20 EE 31
3264
3265
3266
3267 2FF5 A2 10
3268 2FF7 A9 00
3269 2FF9 9D 48 03
3270 2FFC A9 00
3271 2FFE 9D 49 03
3272 3001 FE 48 03
3273 3004 D0 03
3274 3006 FE 49 03
3275 3009 AD E0 19
3276 300C 9D 44 03
3277 300F AD E1 19
3278 3012 9D 45 03
3279 3015 4C 93 18
3280 3018 53 41 56 45
3281 301C 2D 47 49 56
3282 3020 45 20 46 49

; OPEN THE FILE
;
LDA #10
LDA #OPEN
STA ICCOM, X
BIT OPT
BMI **6
LDA #8
BNE **4
LDA #9
STA ICAX1, X
JSR CIOCL

; WRITE SAVE FILE HEADER
;
LDA #PUTCHR
STA ICCOM, X
LDA #. LOW. SAVHL
STA ICBAL, X
LDA #. LOW. SAVHH
STA ICBAL, X
LDA #6
STA ICBLL, X
LDA #0
STA ICBLL, X
LDA #. LOW. LDSTL
STA ICBAL, X
LDA #. LOW. LDSTH
STA ICBAL, X
WHEAD JSR CIOCL

; WRITE DATA RECORD
;
WDR LDA #10
WDR LDA #0
WDR STA ICBLL, X
WDRH LDA #0
WDRH STA ICBLL, X
WDRH STA ICBLL, X
WDRH INC ICBLL, X
WDRH BNE **5
WDRH INC ICBLL, X
WDRH LDA LDST
WDRH STA ICBAL, X
WDRH LDA LDST+1
WDRH STA ICBAL, X
WEX JMP WDR1
SFMG BYTE 'SAVE-GIVE FILE, START, END(, INIT, RUN)', CR
; IF APPEND
; BRANCH IF NOT APPEND
; THIS IMMEDIATE VALUE MODIFIED
; THIS IMMEDIATE VALUE MODIFIED

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 79

3283	3024	4C	45	2C	53
3284	3028	54	41	52	54
3285	302C	2C	45	4E	44
3286	3030	28	2C	49	4E
3287	3034	49	54	2C	52
3288	3038	55	4E	29	9B

```

3289
3290
3291
3292
3293 303C A9 9B
3294 303E A2 4F
3295 3040 9D A4 1D
3296 3043 CA
3297 3044 10 FA
3298 3046 A9 00
3299 3048 8D 01 1F
3300 304B 8D 02 1F
3301 304E 8D F5 1E
3302 3051 20 58 30
3303 3054 20 BB 31
3304 3057 60
3305
3306
3307
3308
3309
3310 3058 A9 05
3311 305A 8D 42 03
3312 305D A9 A4
3313 305F 8D 44 03
3314 3062 A9 1D
3315 3064 8D 45 03
3316 3067 A9 50
3317 3069 8D 48 03
3318 306C A9 00
3319 306E 8D 49 03
3320 3071 A2 00
3321 3073 20 56 E4
3322 3076 C0 80
3323 3078 D0 03
3324 307A CE F5 1E
3325 307D 60
3326
3327
3328
3329
3330 307E A9 00
3331 3080 8D F5 1E
3332 3083 20 58 30
3333 3086 AD 48 03
3334 3089 8D F7 1E
3335 308C 20 BB 31
3336 308F AD F5 1E
3337 3092 10 06
3338 3094 20 AA 19
3339 3097 4C B6 20
3340 309A AD F7 1E
3341 309D C9 03
3342 309F 30 0A

```

```

; **** MISC. SUBROUTINES ****
;
;

```

```

GETLIN LDA #CR
      LDX #79
      STA LINE, X
      DEX
      BPL *-4
      LDA #0
      STA PTR
      STA IPTR
      STA PER
      JSR CIOGET
      JSR SCROL
      RTS
;
;
;

```

```

; CIOGET -- GET LINE OF INPUT FROM SCREEN EDITOR
;

```

```

CIOGET LDA #GETREC
      STA ICCOM          ; SCREEN EDIT IOCB
      LDA #LBUFL
      STA ICBAL
      LDA #LBUFH
      STA ICBALH
      LDA #80
      STA ICBLL
      LDA #0
      STA ICBLLH
      LDX #0
      JSR CIO            ; READ RECORD FROM SCREEN EDITOR
      CPY ##80           ; CHECK FOR BREAK ABORT STATUS
      BNE **+5
      DEC PER            ; PARAM ERROR FLAG IS SET IF SO
      RTS
;
;
;

```

```

; CHRGET -- GET 1 CHAR FROM EDITOR IN A.
;

```

```

CHRGET LDA #0
      STA PER
CHR01 JSR CIOGET          ; GET A LINE FROM E:
      LDA ICBLL           ; SAVE CHAR COUNT
      STA RCNT
      JSR SCROL
      LDA PER
      BPL CHR02           ; IF BREAK, CLOSE AND EXIT
      JSR CLOSX
      JMP MENU5L
CHR02 LDA RCNT            ; EXPECT 1 OR 2 CHARACTERS
      CMP #3
      BMI CHR03           ; IF OK

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 81

3343 30A1 A9 AF

LDA #. LOW. OLL

3344 30A3 A2 30

LDX #. LOW. OLH

3345 30A5 20 B5 31

JSR DSPLIN

3346 30A8 4C B3 30

JMP CHRG1

3347 30AB AD A4 1D

CHRG3

LDA LINE

; TRY AGAIN

3348 30AE 60

RTS

; GET 1ST CHAR

```

3349
3350 30AF 50 4C 45 41
3351 30B3 53 45 20 54
3352 30B7 59 50 45 20
3353 30BB 31 20 4C 45
3354 30BF 54 54 45 52
3355 30C3 9B
3356 30C4
3357 0030
3358 00AF
3359
3360
3361
3362 30C4 2C F5 1E
3363 30C7 30 01
3364 30C9 60
3365 30CA 68
3366 30CB 68
3367 30CC 4C B6 20
3368
3369
3370
3371 30CF 20 3C 30
3372 30D2 A2 10
3373 30D4 20 DD 31
3374 30D7 4C E8 30
3375
3376
3377 30DA A9 08
3378 30DC 8D 03 1F
3379 30DF AC 01 1F
3380 30E2 AE 02 1F
3381 30E5 4C 41 31
3382
3383
3384
3385
3386
3387
3388
3389
3390 30E8 AC 01 1F
3391 30EB AE 02 1F
3392 30EE A9 08
3393 30F0 BD 03 1F
3394
3395
3396
3397 30F3 BD A4 1D
3398 30F6 C9 2C
3399 30F8 F0 3B
3400 30FA C9 9B
3401 30FC F0 37
3402 30FE BD A5 1D

```

```

      .PAGE
OL    .BYTE    'PLEASE TYPE 1 LETTER',CR

```

```

      HILO      OL
+QLH    =      OL/256
+OLL    =      (-256)*OLH+OL

```

```

      ;
      ; PERX - EXIT IF PARAMETER ERRORS
      ;

```

```

PERX    BIT      PER
        BMI      PERX1
        RTS
PERX1   PLA
        PLA
        JMP      MENU5L

```

```

      ;
      ; GETIC1 - READ LINE, GET FILENAME, POINT TO IT IN IOCB1
      ;

```

```

GETIC1  JSR      GETLINE
GETIC2  LDX      #$10
        JSR      PIOCIB
        JMP      GETFIL

```

```

GETNAME LDA      #8          ; ENTRY TO GETFIL USED BY RENAME
        STA      CTR        ; WHICH DOES NOT HAVE A DEVICE ID
        LDY      PTR        ; FOR THE SECOND FILE SPEC
        LDX      IPTR
        JMP      CFTE

```

```

      ;
      ; SUBROUTINE - GETFIL
      ; REMOVES ONE FILE SPECIFICATION FROM THE INPUT LINE.  WILL SET UP
      ; THE SPEC FOR DEFAULTS FOR INCOMPLETE DRIVE ID.  DEFAULT DRIVE #
      ; IS 1.
      ;

```

```

      ; GET FILESPEC FROM INPUT LINE

```

```

GETFIL  LDY      PTR
        LDX      IPTR
        LDA      #11
        STA      CTR

```

```

      ; AVOID GETTING JUNK ON VERY SHORT PARAMS
      ;

```

```

        LDA      LINE,X
        CMP      #'
        BEQ      ADDC
        CMP      #CR
        BEQ      ADDC
        LDA      LINE+1,X

```

```

3403 3101 C9 2C          CMP      #'
3404 3103 F0 22          BEQ      GT1
3405 3105 C9 9B          CMP      #CR
3406 3107 F0 1E          BEQ      GT1
3407 3109 A9 3A          LDA      #'
3408 310B DD A6 1D        CMP      LINE+2,X      ;LOOK FOR : IN FILESPEC
3409 310E F0 31          BEQ      CFTE          ;SEE IF HAVE COMPLETE FILESPEC ALREADY
3410 3110 DD A5 1D        CMP      LINE+1,X
3411 3113 D0 12          BNE      GT1
3412 3115 CE 03 1F        DEC      CTR
3413 3118 BD A4 1D        LDA      LINE,X
3414 311B C9 41          CMP      #'A
3415 311D 10 22          BPL      CFTE          ;HAVE X:FILE, COMPLETE FILESPEC
3416
3417                      ; IF FALLS THRU, IS UNIT:FILE, ADD D
3418
3419 311F A9 44          GT2      LDA      #'D
3420 3121 99 7C 1D        STA      PAR,Y
3421 3124 C8              INY
3422 3125 10 1A          BPL      CFTE
3423 3127 CE 03 1F        GT1      DEC      CTR
3424 312A CE 03 1F        DEC      CTR
3425 312D DD A4 1D        CMP      LINE,X      ;AN UNLIKELY CASE (:FILE)
3426 3130 F0 ED          BEQ      GT2          ;TREAT FILE AS U:FILE
3427 3132 CE 03 1F        DEC      CTR
3428 3135 A9 44          ADDC     LDA      #'D
3429 3137 99 7C 1D        STA      PAR,Y
3430 313A C8              INY
3431 313B A9 3A          LDA      #'
3432 313D 99 7C 1D        STA      PAR,Y
3433 3140 C8              INY
3434 3141 A9 00          CFTE     LDA      #0
3435 3143 8D 9E 15        STA      OPT
3436 3146 BD A4 1D        CFTE1   LDA      LINE,X
3437 3149 99 7C 1D        STA      PAR,Y
3438 314C EB              INX
3439 314D C8              INY
3440 314E C9 9B          CMP      #CR          ;LOOK FOR TERMINATOR
3441 3150 F0 2C          BEQ      EOC
3442 3152 C9 2C          CMP      #'
3443 3154 F0 28          BEQ      EOC
3444 3156 C9 2F          CMP      #'/'
3445 3158 F0 2B          BEQ      POPT
3446 315A C9 2E          CMP      #'
3447 315C D0 05          BNE      CFTE2          ;LOOK FOR START OF .EXT
3448 315E A9 04          LDA      #4          ;FOUND, 4 MORE CHARS MAX
3449 3160 8D 03 1F        STA      CTR
3450 3163 CE 03 1F        CFTE2   DEC      CTR
3451 3166 10 DE          BPL      CFTE1
3452
3453                      ; GETS HERE IF TOO MANY CHARS IN FILENAME
3454
3455 3168 A9 95          LDA      #.LOW.NTLL
3456 316A A2 31          LDX      #.LOW.NTLH

```

```

3457 316C 20 B5 31      JSR      DSPLIN      ; NAME TOO LONG
3458 316F CE F5 1E      DEC      PER          ; SET PARAMETER ERROR FLAG
3459 3172 BD A4 1D      STE      LDA      LINE, X    ; SKIP TO END
3460 3175 E8            INX
3461 3176 C9 2C          CMP      #',
3462 3178 F0 04          BEQ      EOC
3463 317A C9 9B          CMP      #CR
3464 317C D0 F4          BNE      STE
3465 317E 8E 02 1F      EOC      STX      IPTR
3466 3181 8C 01 1F      STY      PTR
3467 3184 60            RTS
3468 3185 BD A4 1D      POPT     LDA      LINE, X
3469 3188 8D 9E 15      STA      OPT
3470 318B E8            INX
3471 318C BD A4 1D      LDA      LINE, X
3472 318F 99 7B 1D      STA      PAR-1, Y    ; CHANGE STORED TERMINATOR TO , OR CR 1 H
3473 3192 E8            INX
3474 3193 10 E9          BPL      EOC
3475 3195 4E 41 4D 45    NTL      BYTE    'NAME TOO LONG', CR
3476 3199 20 54 4F 4F
3477 319D 20 4C 4F 4E
3478 31A1 47 9B
3479 31A3
3480 0031
3481 0095
3482
3483
3484
3485
3486 31A3 A9 0B      DSPMSG  LDA      #PUTCHR
3487 31A5 8D 42 03      STA      ICCOM
3488 31A8 A2 00      LDX      #0
3489
3490 31AA 20 56 E4      CIO1    JSR      CIO          ; CALL CIO AND GO TO MENUSL
3491 31AD C0 80          CPY      ##80        ; IF BREAK KEY ABORT
3492 31AF D0 03          BNE      **5
3493 31B1 4C B6 20      JMP      MENUSL
3494 31B4 60
3495
3496
3497
3498 31B5 20 BE 19      ; DSPLIN - DISPLAY ONE LINE OF TEXT
3499 31B8 4C BB 31      ; A=LO, X=HI ADDRESS
3500
3501
3502
3503
3504 31BB A9 00      DSPLIN  JSR      PRNTMSG    ; USE RESIDENT DUP SUBROUTINE
3505 31BD AA          JMP      SCROL      ; SCROLL SCREEN BELOW MENU & RETURN
3506 31BE 9D 49 03
3507 31C1 A9 0A
3508 31C3 9D 48 03
3509 31C6 A9 31
3510 31C8 9D 45 03      SCROL   LDA      #0
3511
3512
3513
3514
3515
3516
3517
3518
3519
3520
3521
3522
3523
3524
3525
3526
3527
3528
3529
3530
3531
3532
3533
3534
3535
3536
3537
3538
3539
3540
3541
3542
3543
3544
3545
3546
3547
3548
3549
3550
3551
3552
3553
3554
3555
3556
3557
3558
3559
3560
3561
3562
3563
3564
3565
3566
3567
3568
3569
3570
3571
3572
3573
3574
3575
3576
3577
3578
3579
3580
3581
3582
3583
3584
3585
3586
3587
3588
3589
3590
3591
3592
3593
3594
3595
3596
3597
3598
3599
3600
3601
3602
3603
3604
3605
3606
3607
3608
3609
3610
3611
3612
3613
3614
3615
3616
3617
3618
3619
3620
3621
3622
3623
3624
3625
3626
3627
3628
3629
3630
3631
3632
3633
3634
3635
3636
3637
3638
3639
3640
3641
3642
3643
3644
3645
3646
3647
3648
3649
3650
3651
3652
3653
3654
3655
3656
3657
3658
3659
3660
3661
3662
3663
3664
3665
3666
3667
3668
3669
3670
3671
3672
3673
3674
3675
3676
3677
3678
3679
3680
3681
3682
3683
3684
3685
3686
3687
3688
3689
3690
3691
3692
3693
3694
3695
3696
3697
3698
3699
3700
3701
3702
3703
3704
3705
3706
3707
3708
3709
3710
3711
3712
3713
3714
3715
3716
3717
3718
3719
3720
3721
3722
3723
3724
3725
3726
3727
3728
3729
3730
3731
3732
3733
3734
3735
3736
3737
3738
3739
3740
3741
3742
3743
3744
3745
3746
3747
3748
3749
3750
3751
3752
3753
3754
3755
3756
3757
3758
3759
3760
3761
3762
3763
3764
3765
3766
3767
3768
3769
3770
3771
3772
3773
3774
3775
3776
3777
3778
3779
3780
3781
3782
3783
3784
3785
3786
3787
3788
3789
3790
3791
3792
3793
3794
3795
3796
3797
3798
3799
3800
3801
3802
3803
3804
3805
3806
3807
3808
3809
3810
3811
3812
3813
3814
3815
3816
3817
3818
3819
3820
3821
3822
3823
3824
3825
3826
3827
3828
3829
3830
3831
3832
3833
3834
3835
3836
3837
3838
3839
3840
3841
3842
3843
3844
3845
3846
3847
3848
3849
3850
3851
3852
3853
3854
3855
3856
3857
3858
3859
3860
3861
3862
3863
3864
3865
3866
3867
3868
3869
3870
3871
3872
3873
3874
3875
3876
3877
3878
3879
3880
3881
3882
3883
3884
3885
3886
3887
3888
3889
3890
3891
3892
3893
3894
3895
3896
3897
3898
3899
3900
3901
3902
3903
3904
3905
3906
3907
3908
3909
3910
3911
3912
3913
3914
3915
3916
3917
3918
3919
3920
3921
3922
3923
3924
3925
3926
3927
3928
3929
3930
3931
3932
3933
3934
3935
3936
3937
3938
3939
3940
3941
3942
3943
3944
3945
3946
3947
3948
3949
3950
3951
3952
3953
3954
3955
3956
3957
3958
3959
3960
3961
3962
3963
3964
3965
3966
3967
3968
3969
3970
3971
3972
3973
3974
3975
3976
3977
3978
3979
3980
3981
3982
3983
3984
3985
3986
3987
3988
3989
3990
3991
3992
3993
3994
3995
3996
3997
3998
3999
4000

```


ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 85

3511 31CB A9 D3
3512 31CD 9D 44 03
3513 31D0 4C A3 31

LDA #.LOW.ZAPL
STA ICBAL,X
JMP DSPMSG

```

3514      .PAGE
3515 31D3 1C 1C 1C 1C      ZAP      .BYTE      CUP,CUP,CUP,CUP,CUP
3516 31D7 1C
3517 31D8 9C 1D 1D 1D      .BYTE      DLL,CDN,CDN,CDN,CDN
3518 31DC 1D
3519 31DD      HILO      ZAP
3520 0031      +ZAPH      =      ZAP/256
3521 00D3      +ZAPL      =      (-256)*ZAPH+ZAP
3522
3523      ; PIOCBL - POINT IOCB AT PAR(PTR)
3524      ;
3525 31DD A9 7C      PIOCBL LDA      #PARL
3526 31DF 18      CLC
3527 31E0 6D 01 1F      ADC      PTR
3528 31E3 9D 44 03      STA      ICBAL,X
3529 31E6 A9 1D      LDA      #PARH
3530 31E8 69 00      ADC      #0
3531 31EA 9D 45 03      STA      ICBAL,X
3532 31ED 60      RTS
3533
3534      ; CIOCL - CALL CIO AND PROCESS ANY ERRORS
3535      ;
3536 31EE 20 56 E4      CIOCL JSR      CIO      ;CALL CIO
3537 31F1 98      TYA
3538 31F2 30 01      BMI      **3
3539 31F4 60      RTS      ;OK, RETURN
3540 31F5 98      CIOER1 TYA      ;ERROR STATUS
3541 31F6 38      CIOER SEC
3542 31F7 E9 64      SBC      #100      ;ERROR NUMS ALWAYS ARE 1XX DEC
3543 31F9 A2 2F      LDX      #'0-1      ;CONVERT TENS
3544 31FB E8      CTNS INX
3545 31FC 38      SEC
3546 31FD E9 0A      SBC      #10
3547 31FF 10 FA      BPL      CTNS      ;THE EASY (SLOW) WAY
3548 3201 18      CLC
3549 3202 69 3A      ADC      #10+'0      ;CONVERT
3550 3204 8D 22 32      STA      EUN
3551 3207 8E 21 32      STX      ETN
3552 320A A2 32      LDX      #.LOW.CIEH
3553 320C A9 17      LDA      #.LOW.CIEL
3554 320E 20 B5 31      CIEX JSR      DSPLIN
3555 3211 20 AA 19      JSR      CLOSX      ;CLOSE IOCBS 10,20
3556 3214 4C B6 20      JMP      MENUSL
3557 3217 45 52 52 4F      CIE      .BYTE      'ERROR- 1'
3558 321B 52 2D 20 20
3559 321F 20 31
3560 3221 00      ETN      .BYTE      0
3561 3222 00      EUN      .BYTE      0
3562 3223 9B      .BYTE      CR
3563 3224      HILO      CIE
3564 0032      +CIEH      =      CIE/256
3565 0017      +CIEL      =      (-256)*CIEH+CIE
3566
3567

```

```

3568
3569
3570
3571
3572 3224 A9 04
3573 3226 8D 03 1F
3574 3229 A9 00
3575 322B 8D 04 1F
3576 322E 8D 05 1F
3577 3231 AE 02 1F
3578 3234 BD A4 1D
3579 3237 EE 02 1F
3580 323A C9 9B
3581 323C F0 2B
3582 323E C9 2C
3583 3240 F0 27
3584 3242 20 A5 32
3585 3245 30 2A
3586 3247 A0 03
3587 3249 18
3588 324A 2E 05 1F
3589 324D 2E 04 1F
3590 3250 88
3591 3251 10 F6
3592 3253 0D 05 1F
3593 3256 8D 05 1F
3594 3259 CE 03 1F
3595 325C 10 D3
3596 325E A9 77
3597 3260 A2 32
3598 3262 20 B5 31
3599 3265 CE F5 1E
3600 3268 60
3601 3269 A8
3602 326A AD 05 1F
3603 326D AE 04 1F
3604 3270 60
3605 3271 A9 87
3606 3273 A2 32
3607 3275 D0 EB
3608 3277 54 4F 4F 20
3609 327B 4D 41 4E 59
3610 327F 20 44 49 47
3611 3283 49 54 53 9B
3612 3287
3613 0032
3614 0077
3615 3287 49 4E 56 41
3616 328B 4C 49 44 20
3617 328F 48 45 58 41
3618 3293 44 45 43 49
3619 3297 4D 41 4C 20
3620 329B 50 41 52 41
3621 329F 4D 45 54 45

```

```

; GETNO - GET HEX NUMERIC PARAMETER FROM LINE(IPTR).
; RETURN A=LO, X=HI. PER SET MINUS IF ERROR.
; INC IPTR PAST PARAM.
;
GETNO LDA #4 ; MAX NO DIGITS
      STA CTR
      LDA #0
      STA T1
      STA T1+1 ; INIT TEMP TO BUILD NUMBER IN
GHB LDX IPTR ; GET CHAR
    LDA LINE,X
    INC IPTR
    CMP #CR ; SEE IF TERMINATOR
    BEQ GND
    CMP #' '
    BEQ GND
    JSR HEXCON ; CONVERT ASCII TO NIBBLE
    BMI ERRX ; IF ERROR
    LDY #3 ; SHIFT T1,T1+1 BY 4
SHT1 CLC
      ROL T1+1
      ROL T1
      DEY
      BPL SHT1
      ORA T1+1 ; OR IN NEW NIBBLE
      STA T1+1
      DEC CTR
      GHB ; COUNT DIGIT
      LDA #.LOW.TMDL ; LOOP UNLESS TOO MANY DIGITS
      LDX #.LOW.TMDH
ERRX1 JSR DSPLIN
      DEC PER
      RTS
GND TAY
      LDA T1+1
      LDX T1
      RTS
ERRX LDA #.LOW.IHPL ; INVALID HEX PARAM
      LDX #.LOW.IHPH
      BNE ERRX1
TMD . BYTE 'TOO MANY DIGITS',CR

HILO TMD
+TMDH = TMD/256
+TMDL = (-256)*TMDH+TMD
IHP . BYTE 'INVALID HEXADECIMAL PARAMETER',CR

```

```

3622 32A3 52 9B
3623 32A5
3624 0032
3625 0087
3626
3627
3628
3629
3630
3631 32A5 38
3632 32A6 E9 30
3633 32A8 30 0F
3634 32AA C9 0A
3635 32AC 30 0D
3636 32AE 38
3637 32AF E9 07
3638 32B1 C9 0A
3639 32B3 30 04
3640 32B5 C9 10
3641 32B7 30 02
3642 32B9 A9 FF
3643 32BB C9 00
3644 32BD 60
3645
3646
3647
3648
3649 32BE 2C F5 1E
3650 32C1 30 27
3651 32C3 AE 02 1F
3652 32C6 BD A4 1D
3653 32C9 E8
3654 32CA C9 44
3655 32CC F0 F8
3656 32CE 38
3657 32CF E9 30
3658 32D1 F0 18
3659 32D3 30 16
3660 32D5 C9 05
3661 32D7 10 12
3662 32D9 48
3663 32DA BD A4 1D
3664 32DD E8
3665 32DE C9 2C
3666 32E0 F0 04
3667 32E2 C9 9B
3668 32E4 D0 F4
3669 32E6 8E 02 1F
3670 32E9 68
3671 32EA 60
3672 32EB CE F5 1E
3673 32EE A9 F5
3674 32F0 A2 32
3675 32F2 4C B5 31

```

```

HILO IHP
+IHPH = IHP/256
+IHPL = (-256)*IHPH+IHP
)
)
; HEXCON - CONVERT ASCII CHAR IN A TO HEX NIBBLE IN A. RETURN
; MINUS CONDITION, A=FF IF ERROR.
)
HEXCON SEC
SBC #'0
BMI ERRX2 ; ASCII BELOW '0'
CMP #10
BMI OKX ; 0-9 CONVERTED SO EXIT
SEC
SBC #'A-'0-10
CMP #10 ; CONVERTED VALUE MUST BE 10 OR MORE
BMI ERRX2 ; BETWEEN '9' AND 'A'
CMP ##10
BMI OKX ; A-F CONVERTED
ERRX2 LDA ##FF
OKX CMP #0 ; SET STATUS BY VALUE IN A
RTS
)
;
GETDN - GET A DEVICE NUMBER FROM LINE(IPTR)
; RETURN IT IN A
;
GETDN BIT PER ; SEE IF PARAM ERROR ALREADY
BMI GDR ; IF SO DON'T BOTHER
LDX IPTR
GETD LDA LINE,X
INX
CMP #'D ; IF DN
BEQ GETD ; GO GET DIGIT
SEC
SBC #'0 ; CONVERT DIGIT
BEQ BDS ; CAN'T BE ZERO
BMI BDS ; IF NOT DIGIT
CMP #5 ; TOO LARGE
BPL BDS
PHA
GD1 LDA LINE,X
INX
CMP #',
BEQ GD1 ; IF TERMINATOR
CMP #CR
BNE GD1 ; KEEP LOOKING
GD1 STX IPTR ; ADVANCE POINTER
PLA
GDR RTS
BDS DEC PER
LDA #.LOW.NDSL ; NEED DEVICE SPEC MSG
LDX #.LOW.NDSH
JMP DSPLIN

```

ERR LINE ADDR B1 B2 B3 B4

DISK UTILITY PROGRAMS (DUP) VER 2.9 11/18/80

PAGE 89

3676 32F5 4E 45 45 44
 3677 32F9 20 44 31 20
 3678 32FD 54 48 52 55
 3679 3301 20 44 34 9B
 3680 3305 00
 3681 13F9
 3682 3306
 3683 0013
 3684 00F9
 3685 1589
 3686 3306
 3687 0015
 3688 0089
 3689 3306
 3690 0032
 3691 00F5
 3692 3306
 3693 0033
 3694 0005
 3695 3306

NDS . BYTE 'NEED D1 THRU D4',CR

 NMDUP . BYTE 0
 LEN = NMDUP-EDN
 HILO LEN
 +LENH = LEN/256
 +LENL = (-256)*LENH+LEN
 MLEN = NMDUP-NDOS
 HILO MLEN
 +MLENH = MLEN/256
 +MLENL = (-256)*MLENH+MLEN
 HILO NDS
 +NDSH = NDS/256
 +NDSL = (-256)*NDSH+NDS
 HILO NMDUP
 +NMDUPH = NMDUP/256
 +NMDUPL = (-256)*NMDUPH+NMDUP
 . END

ASSEMBLY ERRORS = 0

CROSS REFERENCE

LABEL	VALUE	REFERENCE
AAM	2C59	2571 -2689
ADDC	3135	3399 3401 -3428
ADDOK	2F70	3203 -3205
ADOK	168B	295 298 -315
AF	170C	-383 388 389
AFH	0017	147 -388 389
AFL	000C	145 -389
ANWD	16AE	-331
ASP	2C76	2585 -2704
ASPT	2BA3	2572 -2585
ASPX	2C8C	2709 2711 -2713
AWD	16BB	324 327 332 -336
AWDQ	16FA	323 326 -369
AWDQR	1704	370 -375
BDS	32EB	3658 3659 3661 -3672
BFENHI	0035	-797 846 968
BFENLO	0034	-796 844 966
BLF	294D	-2309 2314 2315
BLFH	0029	2305 -2314 2315
BLFL	004D	2304 -2315
BRKKEY	0011	-27 1180
BRMG	2768	2053 -2066
BRUN	274C	1162 -2053
BSIOR	0772	-51 2737
BUFADR	001A	-119 1834 1837 2869 2871 2944 2946 3027
		3029 3090 3092
BUFLEN	1F04	-1042 1841 1843 2873 2875 3033 3036 3058
		3062 3081 3084 3094 3096
BUFRFL	0038	-802 927 982
BUFRHI	0033	-795 839 845 961 967
BUFRLO	0032	-794 837 843 877 952 959 965
CARTST	BFFA	-33 653
CBIT	2C72	2691 -2698
CDES	1EFF	-1036 1798 1821 1830 1847 1869 1874 2422
		2445 2466 2725
CDN	001D	-57 1147 1147 1147 1147 1147 3517 3517
		3517 3517
CDSK	26EB	1940 -1972
CDTMF3	022A	-53 723 725
CDTMV3	021C	-52 719 720
CFTE	3141	3381 3409 3415 3422 -3434
CFTE1	3146	-3436 3451
CFTE2	3163	3447 -3450
CHKDON	1A0E	857 -869 885
CHKERR	008F	-818 932
CHKSNT	003B	-799 849 856
CHKSUM	0031	-798 854 881 883 930 955 957
CHKTYP	2CFE	2780 -2786
CHKVER	266E	1361 1899 -1920

CHRG1	3083	-3332	3346						
CHRG2	309A	3337	-3340						
CHRG3	30AB	3342	-3347						
CHRGET	307E	1231	1477	1945	2084	2134	2471	2507	2563
		2756	3016	-3330					
CIE	3217	-3557	3564	3565					
CIEH	0032	3552	-3564	3565					
CIEL	0017	3553	-3565						
CIEX	320E	-3554							
CIO	E456	-20	202	218	234	356	439	452	506
		516	582	596	644	687	698	701	716
		735	742	771	1845	1868	1873	2879	2983
		3321	3490	3536					
CIO1	31AA	773	-3490						
CIOCL	31EE	1331	1385	1417	1434	1486	1494	1570	1583
		1593	1608	1686	1785	1822	1855	1906	1955
		2153	2158	2332	2346	2855	2929	2952	2958
		3241	3263	-3536					
CIOER	31F6	1860	2303	-3541					
CIOER1	31F5	2099	2742	2784	2887	-3540			
CIOGET	3058	3302	-3310	3332					
CIOINV	E46E	-25	705						
CKCART	271A	-2019	2024						
CKMDS	157D	144	-154						
CKMEM	20BE	2538	-2748						
CKRS	25FA	1854	-1856						
CLD1	20A5	-2731	2741						
CLDKH	20A0	2721	-2729						
CLDSET	1599	158	-169						
CLF	001E	-58							
CLFX	1646	205	248	-268	275	281			
CLMJP	1912	-649	2038						
CLOC	2606	-1861							
CLOOP	25CB	-1840	1857						
CLOS1	22ED	1487	1489	-1491					
CLOS2	196E	683	-699						
CLOS20	19B4	573	584	-739					
CLOSE	000C	-66	514	699	732	740	1492	1591	1606
		1866	1871	2156	2956	2981			
CLOSX	19AA	152	241	273	278	420	441	455	621
		-732	1714	1803	2092	2307	3338	3555	
CLSCR	007D	-61	1060						
CLSDS	2E00	2940	-2956						
CLSSRC	2E1F	2899	2964	2973	-2980				
CMSI	2A02	-2378	2388	2389					
CMSIH	002A	-2388	2389	2754	3014				
CMSIL	0002	-2389	2753	3013					
COMPR1	2429	-1632	1640						
COMPR2	2434	1634	-1638						
COMPR3	2446	-1648	1655						
COMPR4	2451	1650	-1653						
COMPR5	2456	1644	-1657						
CPMG	231E	-1514	1541						

CPTR1	2CDE	2749	-2762						
CPYFIL	2378	1158	-1541						
CPYFL1	2394	1550	-1552						
CR	009B	-55	383	390	414	539	546	550	559
		1053	1061	1071	1071	1077	1086	1096	1105
		1114	1123	1133	1142	1233	1268	1281	1302
		1312	1344	1372	1472	1483	1495	1504	1514
		1518	1657	1745	1908	1957	1970	1973	2043
		2066	2076	2101	2193	2201	2211	2223	2229
		2309	2316	2334	2348	2358	2366	2378	2475
		2486	2654	2658	2666	2810	3112	3165	3187
		3206	3214	3280	3293	3350	3400	3405	3440
		3463	3475	3562	3580	3608	3615	3667	3676
		-59							
CRT	001F								
CSRC	1EFE	-1035	1328	1685	1770	1782	1829	1840	1848
		1861	2405	2550	2645	2646	2689	2695	2698
CSRCH	001E	-2645	2646	2650					
CSRCL	00FE	-2646	2648						
CTNS	31FB	-3544	3547						
CTR	1F03	-1040	2059	3378	3393	3412	3423	3424	3427
		3449	3450	3573	3594				
CUP	001C	-56	3515	3515	3515	3515	3515		
DB1	1E74	-1014	1020	1021					
DB1H	001E	-1020	1021						
DB1L	0074	-1021							
DB3	1DF1	-1015	1023	1024					
DB3H	001D	-1023	1024	1397	1475				
DB3L	00F1	-1024	1395	1474					
DBLH	0001	-1026							
DBLL	0000	-1025							
DBUF	1DF4	221	223	-1013	1014	1015	1017	1018	1400
		1402	1407	1435	1447	1450	1459	1462	1463
		1470	1473	1484	2270	2404	2694		
DBUFH	001D	209	-1017	1018	1420	2397	3091		
DBUFHI	0305	-88	2398	2582	2584	2590	2627		
DBUFL	00F4	207	-1018	1418	2399	3089			
DBUFLO	0304	-87	2400	2578	2581	2588	2625		
DCB	0300	-83	84	85	86	87	88	89	90
DCDS	2F12	-3165	3173	3174					
DCDSH	002F	3157	-3173	3174					
DCDSL	0012	3156	-3174						
DCOMND	0302	-85	2776						
DDMG	29C2	-2358	2415						
DDSK	26E8	1876	1877	1939	-1969				
DDXT	2CDF	2758	-2764						
DELETE	0021	-72	456	1383	1393				
DELFIL	21C9	1158	-1357						
DELX	22E7	1437	-1489						
DEMG	230D	1357	-1504						
DF1	21F5	1367	-1379						
DINIT	16F7	360	-362						
DIRLST	2139	1158	-1298						
DKHND	E453	-21	2779						

DKWRT	2C98	2577	-2725						
DLL	009C	-60	3517						
DLM	16DB	340	342	-351					
DLM1	16EF	357	-359						
DLMG	21A7	1298	-1344						
DLSTO	2197	-1337	1341						
DLST1	219A	1336	-1338						
DMEND	2057	-1149	1150						
DMENU	1F0F	-1060	1150	1155	1156				
DMENUH	001F	-1155	1156	1210					
DMENUL	000F	-1156	1208						
DOCPY	25AB	1799	-1828						
DODEST	2DA4	2898	-2904						
DODKDP	2B05	2473	-2508						
DODUP	2D66	-2868	2974						
DORD	2B66	-2556	2596						
DOS	1540	-49	127	523	525				
DOSDRV	2875	2115	-2193						
DOSINI	000C	-29	518	520	524	526	667	669	
DOSOS	2075	627	-1175	1177	1178	2186	2188		
DOSOSH	0020	-1177	1178						
DOSOSL	0075	-1178							
DOSTAT	2CF1	-2779	2783						
DOSVEC	000A	-28	131	133					
DOSWDP	2BD2	2567	-2610						
DOTSYS	2415	1613	-1619						
DOW	2B8D	2574	-2577						
DOWRIT	2DE2	2938	-2942						
DPFM	2D08	-2810	2817						
DRRDUP	18EC	624	-627						
DRTS	2CBC	2738	-2743						
DRUN	1621	243	-245						
DRUN1	1635	250	-258						
DRUN2	1644	259	-267						
DRV1	267A	1923	-1926						
DRVSTA	2CE4	2262	2436	2446	-2774				
DS	28CA	2124	2167	-2223	2227	2228	3146		
DSH	0028	2149	-2227	2228					
DSHI	030B	-90	2394	2409	2544	2636	2637	2707	2712
DSHIH	0003	-2636	2637	2650					
DSHIL	000B	-2637	2648						
DSKUTL	2092	-1195							
DSL	00CA	2147	-2228						
DSLMEG	2F57	3193	-3195						
DSLO	030A	-89	2396	2411	2542	2633	2634	2704	2710
DSLOH	0003	-2633	2634	2650					
DSLQL	000A	-2634	2648						
DSPLIN	31B5	1253	1265	1370	1389	1476	1663	1743	1802
		1944	2010	2091	2133	2142	2278	2306	2455
		2470	2506	2535	2562	2752	2755	2831	2895
		2970	2989	3012	3015	3158	3345	3457	-3498
		3554	3598	3675					
DSPMSG	31A3	1216	-3486	3513					

DSTATS	0303	-86							
DTH	1F0C	-1049	1051	1052					
DTHH	001F	-1051	1052	2175					
DTHL	000C	-1052	2173						
DU1	2092	-1196							
DU3	2620	1870	-1874						
DU4	2613	1862	-1869						
DU5	2634	1882	-1884						
DU6	262C	1875	-1879						
DUJPT	2057	-1158	1168	1169					
DUJPTH	0020	-1168	1169	1200					
DUJPTL	0057	-1169	1198						
DULEN	0148	-1150	1152	1153					
DULENH	0001	-1152	1153	1214					
DULENL	0048	-1153	1212						
DUNIT	0301	-84	2718	2726	2774				
DUNUM	000F	-1170	1196						
DUPDSK	2A58	1162	-2415						
DUPFEX	2E3E	2986	-2993						
DUPFIL	2D1E	1166	-2817						
DUPFLG	159D	154	166	-183	258	346	536	651	660
		768							
DUPSYS	182F	528	531	-546	2163				
DVSTAT	02EA	-80	2787						
DWQ	2209	1382	-1387						
EC	182C	-539	541	542					
ECH	0018	-541	542	712					
ECL	002C	-542	710						
EDBLH	0000	-1028	3095						
EDBLL	00FA	-1027	3093						
EDH	001F	-1054	1055						
EDL	000C	-1055							
EDN	1F0C	-1053	1054	1055	3681				
ENUF	2B3A	2532	-2538						
EOC	317E	3441	3443	3462	-3465	3474			
EOF	0088	-62	2885						
EOFFLG	1F0A	-1046	2861	2888	2963				
ERR	1858	490	491	-559					
ERRMES	183A	486	487	-550					
ERROR	17C2	482	-486						
ERRWR	178B	424	440	442	-454				
ERRX	3271	3585	-3605						
ERRX1	3262	-3598	3607						
ERRX2	32B9	3633	3639	-3642					
ERST	164F	219	237	-276	358				
ETN	3221	3551	-3560						
EUN	3222	3550	-3561						
FDP	26EA	-1971	1981	1982					
FDPH	0026	1951	-1981	1982					
FDPL	00EA	1948	-1982						
FINAL	17F7	478	484	-513					
FINDGM	2E82	-3048	3061	3064					
FMINIT	07E0	-48	142						

FMS	0700	-47	48	49						
FMTDSK	2680	1162	-1934							
FMX	2686	1947	-1956							
FORMAT	00FE	-73	1953							
FRMERR	008C	-816	916							
FTRF	1F0B	-1047	1048	2862	2906	2909				
GC1	25AD	-1829								
GD1	32DA	-3663	3668							
GDR	32EA	3650	-3671							
GDX	32E6	3666	-3669							
GETCHR	0007	-68	216	688	1828	2877				
GETD	32C6	-3652	3655							
GETDN	32BE	1936	2120	2419	2421	-3649				
GETFIL	30E8	1321	1695	1731	3374	-3390				
GETIC1	30CF	1299	1358	1542	1895	2289	2327	2341	2818	
		3183	-3371							
GETIC2	30D2	-3372								
GETLIN	303C	1935	2054	2119	2418	2832	2896	2971	2990	
		-3293	3371							
GETMLT	2EA5	3060	-3071							
GETNAM	30DA	1896	-3377							
GETNO	3224	2055	3189	3195	3208	3216	-3572			
GETREC	0005	-69	496	1422	1573	3310				
GHB	3231	-3577	3595							
GLF	2168	1306	-1318							
GND	3269	3581	3583	-3601						
GOOD	17B8	253	475	-481						
GOON	1A78	974	-982							
GOTCOL	2EF6	3138	-3140							
GT1	3127	3404	3406	3411	-3423					
GT2	311F	-3419	3426							
HATABS	031A	-45								
HDBUF	15A0	-186	188	189	287	290	302	303	304	
		305	306	308	315	317	319	320	322	
		325								
HDBUFH	0015	-188	189	228						
HDBUFL	00A0	-189	226							
HEXCON	32A5	3584	-3631							
IBD	2ABF	-2475	2484	2485						
IBDH	002A	2468	-2484	2485						
IBDL	00BF	2469	-2485							
ICAX1	034A	-101	201	422	581	715	1325	1412	1563	
		1680	1781	1818	2152	2854	2912	3240		
ICAX2	034B	-102	1824							
ICBAH	0345	-98	148	210	229	291	309	434	451	
		501	532	579	639	697	713	754	1211	
		1398	1416	1421	1569	1582	1672	1684	1724	
		1838	1839	1952	2150	2872	2928	2947	3250	
		3262	3278	3315	3510	3531				
ICBAHZ	0025	-42								
ICBAL	0344	-97	146	208	227	288	307	432	449	
		499	530	577	637	695	711	753	1209	
		1396	1414	1419	1567	1580	1670	1682	1722	

		1835	1836	1950	2148	2870	2926	2945	3248
ICBALZ	0024	3260	3276	3313	3512	3528			
ICBLH	0349	-41							
		-100	214	233	321	338	438	505	643
		693	761	1215	1433	1578	1844	1851	1852
		2876	2939	2950	2951	3254	3271	3274	3319
		3506							
ICBLL	0348	-99	212	231	318	336	436	503	641
		691	759	1213	1431	1576	1842	1849	1850
		1853	2874	2937	2948	2949	3252	3258	3269
		3272	3317	3333	3508				
ICCOM	0342	-95	199	217	430	447	457	497	515
		575	686	689	700	709	734	741	763
		1327	1384	1394	1410	1423	1493	1565	1574
		1592	1607	1678	1779	1820	1831	1833	1867
		1872	1905	1954	2146	2157	2331	2345	2852
		2878	2914	2943	2957	2982	3234	3246	3311
		3487							
ICDNO	0341	-94							
ICDNOZ	0021	-40							
ICHID	0340	-93							
ICHIDZ	0020	-39							
ICIDNO	002E	-43							
ICSTA	0343	-96							
IDD	2035	-2666	2682	2683					
IDDH	002C	2601	-2682	2683	2893				
IDDL	0035	2600	-2683	2894					
IDRD	223C	-1408	1488						
IHP	3287	-3615	3624	3625					
IHPH	0032	3606	-3624	3625					
IHPL	0087	3605	-3625						
INCOMP	2A99	-2453	2461						
INISAV	179C	-465	519	521	666	668			
INITAD	02E2	-37	353	355	378	600	602	604	607
		3209	3210	3211					
INITIO	1976	472	-705	1191	2029	2062			
INITQ	189F	-597	599	3181	3213				
INITX	1593	149	155	162	-165	170			
INMEM	19DB	769	-773						
INSDS	2D92	2884	-2893						
INTRVE	020A	-34	135	137	139	141			
IOCB	0340	-92	93	94	95	96	97	98	99
		100	101	102					
IOCB1	0010	-78							
IOD	2B90	2576	-2578						
IPTR	1F02	-1039	1391	1440	1481	1693	1697	2407	2548
		2642	2643	2690	2697	3300	3380	3391	3465
		3577	3579	3651	3669				
IPTRH	001F	-2642	2643	2650					
IPTRL	0002	-2643	2648						
IRGEN	D20E	-811	865	1190					
IS12B	2AA3	2447	-2460						
ISD	2C16	-2658	2679	2680					

ISDH	002C	2505	2561	-2679	2680	2829	2968	2987	
ISDISK	2D30	2822	-2825						
ISDL	0016	2504	2560	-2680	2830	2969	2988		
ISRODN	19E6	138	140	-834					
ISRSIR	1A23	134	136	-905					
JMPINT	1705	361	-378						
JMPNWC	2391	1547	-1551						
JMPRUN	1708	244	-379						
JMPTBL	0018	-117	1199	1201	1243	1246			
LBUFH	001D	-1011	1012	3314					
LBUFL	00A4	-1012	3312						
LDFIL	291A	1162	-2288						
LDFX	294A	2299	-2308						
LDMEM	1939	344	594	649	658	-676			
LDMEM1	193F	159	677	-679					
LDMEM2	194A	680	-685						
LDND	19E2	633	634	-784	2178	2184	3196	3197	
LDST	19E0	606	618	631	636	638	-780	782	783
		2174	2176	3190	3191	3199	3202	3275	3277
LDSTH	0019	-782	783	3261					
LDSTL	00E0	-783	3259						
LEN	13F9	-3681	3683	3684					
LENH	0013	2181	-3683	3684					
LENL	00F9	2179	-3684						
LFMG	295B	2288	-2316						
LINE	1DA4	-1010	1011	1012	3295	3347	3397	3402	3408
		3410	3413	3425	3436	3459	3468	3471	3578
		3652	3663						
LKFIL	2970	1158	-2326						
LKMG	2985	2326	-2334						
LMARGN	0052	-31	1184						
LMTR	1920	-658	2063						
LNLF	1648	222	224	-273					
LOAD	15A9	-193	2297						
LOADFG	159F	-185	192	246	247	334	335	339	469
		1182							
LOCK	0023	-74	2329						
LOOKW1	2EEB	3113	-3117						
LOOKW2	2EEC	3109	3111	-3118					
LOOKWC	2ED7	1549	1739	2835	-3106	3115			
LRS	2B7D	-2571	2591						
LRS1	2B7A	2552	2559	-2567	2599				
MAXDEV	0021	-44							
MCONT	27B5	2088	-2097						
MDEND	1A7C	-986	988	989	1001				
MDENDH	001A	-988	989	991					
MDENDL	007C	-989	991						
MDN1	228E	-1447	1454						
MDN2	229E	1449	-1458						
MDN3	22A6	-1462	1467						
MDUPBL	282C	-2163	2166						
MEMFLG	179E	157	-466	468	483	622	676	2761	3025
MEMLDD	170B	215	331	341	343	-382			

MEMLO	02E7	-35							
MEMORY	M 0000	0							
MEMS	277F	-2076	2083						
MEMSAV	279A	1162	-2083						
MEMSG	27BD	-2101	2109	2110					
MEMSGH	0027	2090	-2109	2110					
MEMSGL	00BD	2089	-2110						
MEMSVQ	1873	249	474	-573	679	2087			
MEMTOP	02E5	-26	2518	2522	3030	3034			
MENUSL	20B6	-1222	1266	1290	1371	1386	1490	1594	1744
		1804	1884	1907	1956	2011	2093	2192	2279
		2308	2333	2347	2456	2536	2605	2766	2995
		3159	3204	3339	3367	3493	3556		
MENUSZ	1EF4	-1029	1197	1239					
MERR	27BA	-2099							
MES	249D	-1691							
MLEN	1589	-3685	3687	3688					
MLENH	0015	437	692	-3687	3688				
MLENL	00B9	435	690	-3688					
MLT125	1F06	-1044	3043	3044	3050	3051	3053	3054	3059
		3063	3071	3074	3078	3082			
MNDUP	179F	-467	544	545					
MNDUPH	0017	132	-544	545					
MNDUPL	009F	130	-545						
MNSL	20B6	-1290	1292	1293					
MNSLH	0020	-1292	1293						
MNSLL	00B6	-1293							
MOUT	27AF	2086	-2092	2098					
MOUT1	27B2	2061	-2093						
MWRITE	1746	-420	481	2097					
NAME	1739	-414	418	419					
NAMEH	0017	-418	419	450	578				
NAMEL	003B	-419	448	576					
NARG	0000	0							
NCA	273F	-2040	2045	2046					
NCAH	0027	2009	-2045	2046					
NCAL	003F	2008	-2046						
NCDR	2ADE	-2486	2495	2496					
NCDRH	002A	2454	-2495	2496					
NCDRL	00DE	2453	-2496						
NDF	21E5	-1372	1377	1378					
NDFH	0021	1369	-1377	1378					
NDFL	00E5	1368	-1378						
NDOS	1D7C	-1001	1003	1004	1005	3685			
NDOSH	001D	369	433	696	-1003	1004			
NDOSL	007C	431	694	-1004					
NDS	32F5	-3676	3690	3691					
NDSH	0032	3192	3674	-3690	3691				
NDSL	00F5	3673	-3691						
NINTAD	2F88	3212	-3214						
NLF	2940	2301	-2304						
NMDUP	3305	2177	2183	-3680	3681	3685	3693	3694	
NMDUPH	0033	371	2510	3028	3035	-3693	3694		

NMDUPL	0005	2508	3026	3032	-3694				
NMSF	171B	-390	399	400					
NMSFH	0017	261	-399	400					
NMSFL	001B	260	-400						
NOCART	270A	-2008	2016	2020	2022				
NOCKSM	003C	-800	973	977					
NORM	2B30	-2533							
NORNAD	18DB	610	-621						
NOSYS	241B	1614	-1621						
NOT256	2CAD	2733	-2735						
NOTEND	1A12	847	-876						
NOTN	292E	2294	-2296						
NOTRAM	2714	2001	2005	-2015					
NOTSAM	2F11	3148	-3163						
NOTWC	24E1	1551	-1728						
NOTYET	1A50	928	-950						
NOWC	2D4A	2836	-2840						
NOWRPO	19EE	838	-843						
NRM	2C06	-2654	2676	2677					
NRMH	002C	2534	-2676	2677					
NRML	0006	2533	-2677						
NRUNAD	2FA0	2191	3207	3215	3221	-3223			
NSI	210D	-1268	1285	1286					
NSIH	0021	1264	-1285	1286					
NSIL	000D	1263	-1286						
NTFRAM	1A31	915	-919						
NTL	3195	-3475	3480	3481					
NTLH	0031	3456	-3480	3481					
NTLL	0095	3455	-3481						
NTOVRN	1A39	920	-927						
NTWRP1	1A64	960	-965						
NWA	2501	-1745	1756	1757					
NWAH	0025	1742	-1756	1757					
NWAL	0001	1741	-1757						
NWCIND	2527	1740	-1758						
NXS	2C84	2706	-2710						
NXTCHA	2EF9	-3146	3152						
QDMS	2574	1716	1764	1766	1773	1793	-1800	1807	1813
		2823							
OE	232E	-1518	1524	1525					
OEH	0023	-1524	1525	1801					
OEL	002E	-1525	1800						
OK	29DF	-2366	2376	2377					
OKH	0029	-2376	2377	2751	3011				
OKL	00DF	-2377	2750	3010					
OKTYP	2905	2263	-2269						
OKX	32BB	3635	3641	-3643					
OL	30AF	-3350	3357	3358					
OLH	0030	3344	-3357	3358					
OLL	00AF	3343	-3358						
ONE28	2A8C	2437	-2445						
OPDES	2581	1796	-1806						
OPDES1	2594	1725	1811	-1816					

OPDES3	2596	1815	-1817						
OPEN	0003	-65	198	446	574	685	708	1326	1409
		1564	1677	1778	1819	2144	2851	2913	3233
OPNDES	2DB2	2907	-2911						
OPSRC	2544	1768	-1772						
OPT	159E	129	-184	242	359	534	1380	1808	2291
		2292	2295	2540	2557	2573	2595	2597	2603
		3184	3224	3228	3235	3255	3435	3469	
ORDWRT	000C	-106	580	714					
OREST	1779	423	-446	458					
OVRUN	008E	-817	921						
OWRIT	0008	-105	421						
PAR	1D7C	-1007	1008	1009	1303	1304	1308	1309	1311
		1313	1339	1365	1403	1545	1566	1568	1622
		1701	1707	1762	1790	1921	2164	2168	2820
		3106	3136	3147	3188	3420	3429	3432	3437
		3472							
PARH	001D	-1008	1009	1415	2919	3529			
PARL	007C	-1009	1413	2918	3525				
PDES	255E	1337	1704	1771	-1789				
PDES1	256C	1342	-1797						
PER	1EF5	-1030	2897	2972	3301	3324	3331	3336	3362
		3458	3599	3649	3672				
PERX	30C4	1322	1359	1759	1897	1941	2056	2121	2296
		2328	2342	2423	2819	2833	2991	3217	-3362
PERX1	30CA	3363	-3365						
PIOCB	31DD	1320	1689	1730	2172	3373	-3525		
POKMSK	0010	-804	862	864	1187	1189			
POPT	3185	3445	-3468						
PRNTMS	19BE	262	488	492	-753	1228	1878	3498	
PSRC	252D	-1761							
PTR	1F01	-1038	1301	1317	1332	1425	1438	1439	1480
		1543	1690	1699	2170	2403	2546	2639	2640
		2692	2693	3186	3299	3379	3390	3466	3527
PTRH	001F	-2639	2640	2650					
PTRL	0001	-2640	2648						
PUTCHR	000B	-67	429	1832	2942	3245	3486		
PUTREC	0009	-70	762						
QWMG	28AB	2125	-2211	2221	2222				
QWMGH	0028	2132	-2221	2222					
QWMGL	00AB	2131	-2222						
RAMLO	001A	-118	119	662	1245	1247	1249	1252	1255
		1258	1259	1261	1262	2057	2058	2612	2614
		2616	2619						
RANGE	2103	1238	1240	-1263					
RCNT	1EF7	-1032	2730	2740	2778	2782	3334	3340	
RDDRC	15F7	-225	362						
RDDRC1	1605	-231	311						
RDFN	2269	-1429	1441	1479					
RDLF	15C8	203	-206						
RECVDN	0039	-803	938						
RELDIN	192E	161	347	652	661	-666			
RELONE	1A05	850	-862						

RENAME	0020	-71	1903						
RENFIL	2637	1158	-1894						
REPLAC	2EB2	3072	3075	-3078					
RET	1778	-444							
RETSTA	2D07	2789	-2791						
RMARGN	0053	-32	1186						
RNMG	2652	1894	-1908						
ROMTST	BFFD	-1996	1997	1999	2000	2003	2004	2007	2019
		2021							
RRDUP	1801	263	-518						
RRDUP1	1813	-528	626						
RSEC1	2C8D	2401	2575	-2717					
RTCART	182B	509	-538						
RTS	1647	193	195	-269	352	354			
RUNAD	02E0	-38	194	196	379	612	614	616	619
		2187	2189	3218	3219	3220			
RUNG	18BD	598	-609	611	2190	3182	3222		
RVTOC	2A26	2269	-2393	2541					
SAME	2AAB	2449	-2465						
SAVFIL	2F2E	1162	-3179						
SAVH	19DE	-776	778	779					
SAVHH	0019	-778	779	3249					
SAVHL	00DE	-779	3247						
SAVX	1F00	-1037	1318	1334	1338	1468	1482	1544	1700
		1735	1738	1789					
SCMG	274B	1995	-2043						
SCROL	31BB	1254	3303	3335	3499	-3504			
SDD	2AFB	2467	-2504						
SECSIZ	1F08	-1045	2260	2265	2431	2433	2439	2441	2448
		2460	2520	2523	2580	2583	2732		
SERIN	D20D	-810	929	950					
SEROUT	D20D	-809	810	855	878				
SETFLG	2D8F	2886	-2888						
SETVBV	E45C	-22	724	2033	2037				
SFLOAD	15A4	-191	537						
SFMG	301B	3179	-3280						
SHFLOK	02BE	-36	1230						
SHMEN	209F	-1208	1234						
SHT1	3249	-3587	3591						
SIT	211A	-1275	-1288	1289					
SITH	0021	1227	-1288	1289					
SITL	001A	1226	-1289						
SKIP1	23FB	1599	-1604						
SKIPWC	2DC8	2921	-2926						
SKRES	D20A	-808	911						
SKSTAT	D20F	-812	910						
SMVRS	2919	2272	-2283						
SRETRN	1A48	931	-937	978					
SSTAT	1EF8	-1033	1846	1856					
STACK	S 0000	0							
STAK	0100	507	-993	995	996				
STAKH	0001	500	-995	996					
STAKL	0000	498	-996						

STAREQ	0053	-76	2775						
STATUS	0030	-801	917	922	933				
STCAR	26EE	1158	-1995						
STDD	28B6	-2595							
STDD1	28CA	2586	-2603						
STDD2	28BB	-2597	2604						
STE	3172	-3459	3464						
STLOAD	15A6	151	-192						
STOK	1658	235	-286						
STVEC	1F06	-1043	1044	2509	2511	2529	2531	2624	2626
SUSUAL	1A4C	-942	969	983					
SWATH	2C01	2613	-2650						
SWATL	2BFC	2611	-2648						
SWDP	1EF9	-1034	2543	2545	2547	2549	2551	2618	2621
SWLOP	2BD4	-2611	2623						
SYSER	0000	-104							
SYSLOP	2408	-1612	1616						
SYSVBV	E45F	-23	1987						
SYVBL	E45F	-1987	1989	1990					
SYVBLH	00E4	-1989	1990	2031					
SYVBLL	005F	-1990	2032						
T1	1F04	-1041	1042	2521	2524	2528	2530	2587	2589
		3575	3576	3588	3589	3592	3593	3602	3603
TEMP	1799	454	-459						
TMD	3277	-3608	3613	3614					
TMDH	0032	3597	-3613	3614					
TMDL	0077	3596	-3614						
TSTDOS	2EED	1736	2845	-3135					
TSTVER	28F3	1928	2127	-2258					
TWODRV	1F0B	-1048	2417	2472	2558	2598			
TYQ	22F7	-1495	1502	1503					
TYQH	0022	1388	-1502	1503					
TYQL	00F7	1387	-1503						
ULFIL	2998	1158	-2340						
ULMG	29AD	2340	-2348						
UNLOCK	0024	-75	2343						
UNNO	1EF6	-1031	1926	2122	2261	2420	2435	2465	2717
USEBUF	2EC4	1300	3018	-3089					
USED84	2E5A	3009	-3023						
USEPGM	2E41	1675	1760	2825	-3008				
USRDOS	1700	-46							
VECTR	19E4	601	603	613	615	-785			
VFM	26D0	-1963	1978	1979					
VFMH	0026	1943	-1978	1979					
VFML	00D0	1942	-1979						
WAITIM	19A4	-725	726						
WARMST	0008	-30	143	169	471	477	511	682	2748
		2760	3008	3024					
WBMG	2892	-2201	2208	2209					
WBMGH	0028	2141	-2208	2209					
WBMGL	0092	2140	-2209						
WBOOT	27D9	1162	-2115						
WBX	2872	2136	-2192						

WCBUF	2344	-1535	1579	1581	1585	1612	1632	1642	1648
WCBUF2	2364	-1539	1626	1635	1646	1651	1658	1669	1671
		1681	1683	1712	1720	1721	1723	2923	2924
WCBUFL	0014	-1534	1575						
WCDUPS	2D4F	1673	-2850						
WCFLAG	2341	1225	-1531	1555	1665	1881	2920	2985	
WCGOT	23EE	1587	1589	-1597					
WCGOT1	2422	1624	-1626						
WCINIT	2396	-1555	2838						
WCOPY	2476	1666	-1675						
WCOPYO	24BA	1703	-1706						
WCOPY1	24C4	1709	-1712						
WCOPY2	24CF	1713	-1719						
WCOPYL	239E	-1559	1617	1883	2992				
WCOPYM	2358	-1536	1661	1662					
WCOPYR	23BC	-1573	1602						
WCSKP1	2342	-1532	1557	1597	1604				
WCSKP2	2343	-1533	1560	1598	1601				
WDR	2FF5	-3267							
WDR1	1893	-592	623	625	3194	3279			
WDR2	189A	593	-595						
WDRH	2FFC	2182	3205	-3270					
WDRL	2FF7	2180	3200	-3268					
WEX	3015	-3279							
WHD	26B9	1934	-1957	1975	1976				
WHDH	0026	-1975	1976						
WHDL	00B9	-1976							
WHEAD	2FF2	3256	-3263						
WRMSTR	E474	-50	163						
WRVEC	18EF	608	620	-631					
WVD	28D5	-2229	2238	2239					
WVDH	0028	-2238	2239	2277					
WVDL	00D5	-2239	2276						
XBLK	2B74	-2562	2602						
XITVBV	E462	-24	1991						
XTVBL	E462	-1991	1993	1994					
XTVBLH	00E4	-1993	1994	2035					
XTVBLL	0062	-1994	2036						
ZAP	31D3	-3515	3520	3521					
ZAPH	0031	3509	-3520	3521					
ZAPL	00D3	3511	-3521						

